

Key: AESExport\_DE\_IN\_XML\_AI  
XSD: interfaceDescription\_AESExport\_DE\_IN\_XML\_AI - Ausfuhranmeldung - 1.9.0.xsd  
Document-Version: interfaceDescription\_AESExport\_DE\_IN\_XML\_AI - Ausfuhranmeldung - 1.9.0  
Notes:

1	Root
1.1	Root.Client
1.2	Root.User
1.3	Root.CountryOfLodgement
1.4	Root.OperationDomain
1.5	Root.OperationType
1.6	Root.ID
1.7	Root.ReferenceNumber
1.8	Root.AdditionalReferenceNumber
1.9	Root.StatusNotificationEmail
1.10	Root.Meta
1.10.1	Root.Meta.Operation
1.10.2	Root.Meta.ReferenceType
1.10.3	Root.Meta.CopyTemplate
1.10.3.1	Root.Meta.CopyTemplate.Reference
1.10.3.2	Root.Meta.CopyTemplate.ReferenceType
1.10.4	Root.Meta.ShipmentNumber
1.10.5	Root.Meta.PreventFloodingArticleData
1.10.6	Root.Meta.TransferAuthorisationFromMasterData
1.10.7	Root.Meta.PerformUserDefinedActions
1.10.8	Root.Meta.AllocationNetMass
1.10.9	Root.Meta.AllocationInvoiceAmount
1.10.10	Root.Meta.PositionReference
1.10.10.1	Root.Meta.PositionReference.DeclarationGoodsItemNumber
1.10.10.2	Root.Meta.PositionReference.CalculateStatisticalValue
1.10.10.3	Root.Meta.PositionReference.StockSelection
1.10.10.3.1	Root.Meta.PositionReference.StockSelection.RegistrationID
1.10.10.3.2	Root.Meta.PositionReference.StockSelection.WarehouseAccountNumber
1.10.10.3.3	Root.Meta.PositionReference.StockSelection.LvsID
1.10.10.3.4	Root.Meta.PositionReference.StockSelection.DisposerWarehouse
1.10.10.3.5	Root.Meta.PositionReference.StockSelection.ArticleNumber
1.10.10.3.6	Root.Meta.PositionReference.StockSelection.StorageProcedureCode
1.10.10.3.7	Root.Meta.PositionReference.StockSelection.StorageLocationCode
1.10.10.3.8	Root.Meta.PositionReference.StockSelection.AuthorisationReferenceNumber
1.10.10.3.9	Root.Meta.PositionReference.StockSelection.AdditionalReferenceNumber
1.11	Root.Transition
1.11.1	Root.Transition.TransitionType
1.11.2	Root.Transition.LRN
1.11.3	Root.Transition.DeclarationType
1.11.4	Root.Transition.ExportDeclarationType
1.11.5	Root.Transition.PartyConstellation
1.11.6	Root.Transition.DeclarationSubmissionDateAndTime
1.11.7	Root.Transition.DeclarationSubmissionTimezone
1.11.8	Root.Transition.DecisiveDate
1.11.9	Root.Transition.ExitDate
1.11.10	Root.Transition.PresentationStartDateAndTime
1.11.11	Root.Transition.PresentationStartTimezone
1.11.12	Root.Transition.LoadingEndDateAndTime
1.11.13	Root.Transition.LoadingEndTimezone
1.11.14	Root.Transition.Security
1.11.15	Root.Transition.SpecificCircumstanceIndicator
1.11.16	Root.Transition.TransportCosts
1.11.17	Root.Transition.TransportCostsCurrency
1.11.18	Root.Transition.TotalAmountInvoiced
1.11.19	Root.Transition.InvoiceCurrency
1.11.20	Root.Transition.Authorisation
1.11.20.1	Root.Transition.Authorisation.SequenceNumber
1.11.20.2	Root.Transition.Authorisation.Type
1.11.20.3	Root.Transition.Authorisation.ReferenceNumber
1.11.21	Root.Transition.CustomsOfficeOfPresentation
1.11.22	Root.Transition.CustomsOfficeOfExport

1.11.23	Root.Transition.CustomsOfficeOfSupplement
1.11.24	Root.Transition.CustomsOfficeOfExitDeclared
1.11.25	Root.Transition.CustomsOfficeOfExitActual
1.11.26	Root.Transition.ContractualPartner
1.11.26.1	Root.Transition.ContractualPartner.Code
1.11.26.2	Root.Transition.ContractualPartner.IdentificationNumber
1.11.26.3	Root.Transition.ContractualPartner.SubsidiaryNumber
1.11.26.4	Root.Transition.ContractualPartner.Name
1.11.26.5	Root.Transition.ContractualPartner.Address
1.11.26.5.1	Root.Transition.ContractualPartner.Address.StreetAndNumber
1.11.26.5.2	Root.Transition.ContractualPartner.Address.Postcode
1.11.26.5.3	Root.Transition.ContractualPartner.Address.City
1.11.26.5.4	Root.Transition.ContractualPartner.Address.Country
1.11.27	Root.Transition.Exporter
1.11.27.1	Root.Transition.Exporter.Code
1.11.27.2	Root.Transition.Exporter.IdentificationNumber
1.11.27.3	Root.Transition.Exporter.SubsidiaryNumber
1.11.27.4	Root.Transition.Exporter.Name
1.11.27.5	Root.Transition.Exporter.Address
1.11.27.5.1	Root.Transition.Exporter.Address.StreetAndNumber
1.11.27.5.2	Root.Transition.Exporter.Address.Postcode
1.11.27.5.3	Root.Transition.Exporter.Address.City
1.11.27.5.4	Root.Transition.Exporter.Address.Country
1.11.28	Root.Transition.Declarant
1.11.28.1	Root.Transition.Declarant.Code
1.11.28.2	Root.Transition.Declarant.IdentificationNumber
1.11.28.3	Root.Transition.Declarant.SubsidiaryNumber
1.11.28.4	Root.Transition.Declarant.Name
1.11.28.5	Root.Transition.Declarant.Address
1.11.28.5.1	Root.Transition.Declarant.Address.StreetAndNumber
1.11.28.5.2	Root.Transition.Declarant.Address.Postcode
1.11.28.5.3	Root.Transition.Declarant.Address.City
1.11.28.5.4	Root.Transition.Declarant.Address.Country
1.11.28.6	Root.Transition.Declarant.ContactPerson
1.11.28.6.1	Root.Transition.Declarant.ContactPerson.Name
1.11.28.6.2	Root.Transition.Declarant.ContactPerson.PhoneNumber
1.11.28.6.3	Root.Transition.Declarant.ContactPerson.EMailAddress
1.11.29	Root.Transition.Representative
1.11.29.1	Root.Transition.Representative.Code
1.11.29.2	Root.Transition.Representative.IdentificationNumber
1.11.29.3	Root.Transition.Representative.SubsidiaryNumber
1.11.29.4	Root.Transition.Representative.ContactPerson
1.11.29.4.1	Root.Transition.Representative.ContactPerson.Name
1.11.29.4.2	Root.Transition.Representative.ContactPerson.PhoneNumber
1.11.29.4.3	Root.Transition.Representative.ContactPerson.EMailAddress
1.11.30	Root.Transition.SubContractor
1.11.30.1	Root.Transition.SubContractor.Code
1.11.30.2	Root.Transition.SubContractor.IdentificationNumber
1.11.30.3	Root.Transition.SubContractor.SubsidiaryNumber
1.11.30.4	Root.Transition.SubContractor.Name
1.11.30.5	Root.Transition.SubContractor.Address
1.11.30.5.1	Root.Transition.SubContractor.Address.StreetAndNumber
1.11.30.5.2	Root.Transition.SubContractor.Address.Postcode
1.11.30.5.3	Root.Transition.SubContractor.Address.City
1.11.30.5.4	Root.Transition.SubContractor.Address.Country
1.11.31	Root.Transition.GoodsShipment
1.11.31.1	Root.Transition.GoodsShipment.NatureOfTransaction
1.11.31.2	Root.Transition.GoodsShipment.CountryOfExport
1.11.31.3	Root.Transition.GoodsShipment.CountryOfDestination
1.11.31.4	Root.Transition.GoodsShipment.AdditionalSupplyChainActor
1.11.31.4.1	Root.Transition.GoodsShipment.AdditionalSupplyChainActor.SequenceNumber

1.11.31.4.2	Root.Transition.GoodsShipment.AdditionalSupplyChainActor.Role
1.11.31.4.3	Root.Transition.GoodsShipment.AdditionalSupplyChainActor.Code
1.11.31.4.4	Root.Transition.GoodsShipment.AdditionalSupplyChainActor.IdentificationNumber
1.11.31.5	Root.Transition.GoodsShipment.DeliveryTerms
1.11.31.5.1	Root.Transition.GoodsShipment.DeliveryTerms.IncotermsCode
1.11.31.5.2	Root.Transition.GoodsShipment.DeliveryTerms.UNLocode
1.11.31.5.3	Root.Transition.GoodsShipment.DeliveryTerms.Location
1.11.31.5.4	Root.Transition.GoodsShipment.DeliveryTerms.Country
1.11.31.5.5	Root.Transition.GoodsShipment.DeliveryTerms.Text
1.11.31.6	Root.Transition.GoodsShipment.OutwardProcessing
1.11.31.6.1	Root.Transition.GoodsShipment.OutwardProcessing.Reimport
1.11.31.6.1.1	Root.Transition.GoodsShipment.OutwardProcessing.Reimport.SequenceNumber
1.11.31.6.1.2	Root.Transition.GoodsShipment.OutwardProcessing.Reimport.Country
1.11.31.6.2	Root.Transition.GoodsShipment.OutwardProcessing.IdentificationMeans
1.11.31.6.2.1	Root.Transition.GoodsShipment.OutwardProcessing.IdentificationMeans.SequenceNumber
1.11.31.6.2.2	Root.Transition.GoodsShipment.OutwardProcessing.IdentificationMeans.Type
1.11.31.6.2.3	Root.Transition.GoodsShipment.OutwardProcessing.IdentificationMeans.Description
1.11.31.6.3	Root.Transition.GoodsShipment.OutwardProcessing.Product
1.11.31.6.3.1	Root.Transition.GoodsShipment.OutwardProcessing.Product.SequenceNumber
1.11.31.6.3.2	Root.Transition.GoodsShipment.OutwardProcessing.Product.DescriptionOfGoods
1.11.31.6.3.3	Root.Transition.GoodsShipment.OutwardProcessing.Product.CommodityCode
1.11.31.7	Root.Transition.GoodsShipment.PreviousDocument
1.11.31.7.1	Root.Transition.GoodsShipment.PreviousDocument.SequenceNumber
1.11.31.7.2	Root.Transition.GoodsShipment.PreviousDocument.TypeAndQualifier
1.11.31.7.3	Root.Transition.GoodsShipment.PreviousDocument.ReferenceNumber
1.11.31.8	Root.Transition.GoodsShipment.SupportingDocument
1.11.31.8.1	Root.Transition.GoodsShipment.SupportingDocument.SequenceNumber
1.11.31.8.2	Root.Transition.GoodsShipment.SupportingDocument.TypeAndQualifier
1.11.31.8.3	Root.Transition.GoodsShipment.SupportingDocument.ReferenceNumber
1.11.31.8.4	Root.Transition.GoodsShipment.SupportingDocument.DocumentLineItemNumber
1.11.31.8.5	Root.Transition.GoodsShipment.SupportingDocument.IssuingAuthorityName
1.11.31.8.6	Root.Transition.GoodsShipment.SupportingDocument.IssuingDate
1.11.31.8.7	Root.Transition.GoodsShipment.SupportingDocument.ValidityDate
1.11.31.9	Root.Transition.GoodsShipment.AdditionalReference
1.11.31.9.1	Root.Transition.GoodsShipment.AdditionalReference.SequenceNumber
1.11.31.9.2	Root.Transition.GoodsShipment.AdditionalReference.TypeAndQualifier
1.11.31.9.3	Root.Transition.GoodsShipment.AdditionalReference.ReferenceNumber
1.11.31.10	Root.Transition.GoodsShipment.AdditionalInformation
1.11.31.10.1	Root.Transition.GoodsShipment.AdditionalInformation.SequenceNumber
1.11.31.10.2	Root.Transition.GoodsShipment.AdditionalInformation.Code
1.11.31.10.3	Root.Transition.GoodsShipment.AdditionalInformation.Text
1.11.31.11	Root.Transition.GoodsShipment.Consignment
1.11.31.11.1	Root.Transition.GoodsShipment.Consignment.ContainerIndicator
1.11.31.11.2	Root.Transition.GoodsShipment.Consignment.InlandModeOfTransport
1.11.31.11.3	Root.Transition.GoodsShipment.Consignment.ModeOfTransportAtTheBorder
1.11.31.11.4	Root.Transition.GoodsShipment.Consignment.GrossMass
1.11.31.11.5	Root.Transition.GoodsShipment.Consignment.ReferenceNumberUCR
1.11.31.11.6	Root.Transition.GoodsShipment.Consignment.RegistrationNumberExternal
1.11.31.11.7	Root.Transition.GoodsShipment.Consignment.Carrier
1.11.31.11.7.1	Root.Transition.GoodsShipment.Consignment.Carrier.Code
1.11.31.11.7.2	Root.Transition.GoodsShipment.Consignment.Carrier.IdentificationNumber
1.11.31.11.7.3	Root.Transition.GoodsShipment.Consignment.Carrier.SubsidiaryNumber
1.11.31.11.8	Root.Transition.GoodsShipment.Consignment.Consignor
1.11.31.11.8.1	Root.Transition.GoodsShipment.Consignment.Consignor.Code
1.11.31.11.8.2	Root.Transition.GoodsShipment.Consignment.Consignor.IdentificationNumber
1.11.31.11.8.3	Root.Transition.GoodsShipment.Consignment.Consignor.SubsidiaryNumber
1.11.31.11.8.4	Root.Transition.GoodsShipment.Consignment.Consignor.Name
1.11.31.11.8.5	Root.Transition.GoodsShipment.Consignment.Consignor.Address
1.11.31.11.8.5.1	Root.Transition.GoodsShipment.Consignment.Consignor.Address.StreetAndNumber
1.11.31.11.8.5.2	Root.Transition.GoodsShipment.Consignment.Consignor.Address.Postcode
1.11.31.11.8.5.3	Root.Transition.GoodsShipment.Consignment.Consignor.Address.City

1.11.31.11.8.5.4	Root.Transition.GoodsShipment.Consignment.Consignor.Address.Country
1.11.31.11.9	Root.Transition.GoodsShipment.Consignment.Consignee
1.11.31.11.9.1	Root.Transition.GoodsShipment.Consignment.Consignee.Code
1.11.31.11.9.2	Root.Transition.GoodsShipment.Consignment.Consignee.IdentificationNumber
1.11.31.11.9.3	Root.Transition.GoodsShipment.Consignment.Consignee.SubsidiaryNumber
1.11.31.11.9.4	Root.Transition.GoodsShipment.Consignment.Consignee.Name
1.11.31.11.9.5	Root.Transition.GoodsShipment.Consignment.Consignee.Address
1.11.31.11.9.5.1	Root.Transition.GoodsShipment.Consignment.Consignee.Address.StreetAndNumber
1.11.31.11.9.5.2	Root.Transition.GoodsShipment.Consignment.Consignee.Address.Postcode
1.11.31.11.9.5.3	Root.Transition.GoodsShipment.Consignment.Consignee.Address.City
1.11.31.11.9.5.4	Root.Transition.GoodsShipment.Consignment.Consignee.Address.Country
1.11.31.11.10	Root.Transition.GoodsShipment.Consignment.TransportEquipment
1.11.31.11.10.1	Root.Transition.GoodsShipment.Consignment.TransportEquipment.SequenceNumber
1.11.31.11.10.2	Root.Transition.GoodsShipment.Consignment.TransportEquipment.ContainerIdentificationNumber
1.11.31.11.10.3	Root.Transition.GoodsShipment.Consignment.TransportEquipment.GoodsReference
1.11.31.11.10.3.1	Root.Transition.GoodsShipment.Consignment.TransportEquipment.GoodsReference.SequenceNumber
1.11.31.11.10.3.2	Root.Transition.GoodsShipment.Consignment.TransportEquipment.GoodsReference.DeclarationGoodsItemNumber
1.11.31.11.11	Root.Transition.GoodsShipment.Consignment.LocationOfGoods
1.11.31.11.11.1	Root.Transition.GoodsShipment.Consignment.LocationOfGoods.TypeOfLocation
1.11.31.11.11.2	Root.Transition.GoodsShipment.Consignment.LocationOfGoods.QualifierOfIdentification
1.11.31.11.11.3	Root.Transition.GoodsShipment.Consignment.LocationOfGoods.AuthorisationNumber
1.11.31.11.11.4	Root.Transition.GoodsShipment.Consignment.LocationOfGoods.AdditionalIdentifier
1.11.31.11.11.5	Root.Transition.GoodsShipment.Consignment.LocationOfGoods.UNLocode
1.11.31.11.11.6	Root.Transition.GoodsShipment.Consignment.LocationOfGoods.GNSSLatitude
1.11.31.11.11.7	Root.Transition.GoodsShipment.Consignment.LocationOfGoods.GNSSLongitude
1.11.31.11.11.8	Root.Transition.GoodsShipment.Consignment.LocationOfGoods.Address
1.11.31.11.11.8.1	Root.Transition.GoodsShipment.Consignment.LocationOfGoods.Address.ComplementOfInformation
1.11.31.11.11.8.2	Root.Transition.GoodsShipment.Consignment.LocationOfGoods.Address.StreetAndNumber
1.11.31.11.11.8.3	Root.Transition.GoodsShipment.Consignment.LocationOfGoods.Address.Postcode
1.11.31.11.11.8.4	Root.Transition.GoodsShipment.Consignment.LocationOfGoods.Address.City
1.11.31.11.11.8.5	Root.Transition.GoodsShipment.Consignment.LocationOfGoods.Address.Country
1.11.31.11.11.9	Root.Transition.GoodsShipment.Consignment.LocationOfGoods.ContactPerson
1.11.31.11.11.9.1	Root.Transition.GoodsShipment.Consignment.LocationOfGoods.ContactPerson.Name
1.11.31.11.11.9.2	Root.Transition.GoodsShipment.Consignment.LocationOfGoods.ContactPerson.PhoneNumber
1.11.31.11.11.9.3	Root.Transition.GoodsShipment.Consignment.LocationOfGoods.ContactPerson.EmailAddress
1.11.31.11.12	Root.Transition.GoodsShipment.Consignment.DepartureTransportMeans
1.11.31.11.12.1	Root.Transition.GoodsShipment.Consignment.DepartureTransportMeans.SequenceNumber
1.11.31.11.12.2	Root.Transition.GoodsShipment.Consignment.DepartureTransportMeans.TypeOfIdentification
1.11.31.11.12.3	Root.Transition.GoodsShipment.Consignment.DepartureTransportMeans.IdentificationNumber
1.11.31.11.12.4	Root.Transition.GoodsShipment.Consignment.DepartureTransportMeans.Nationality
1.11.31.11.13	Root.Transition.GoodsShipment.Consignment.CountryOfRoutingOfConsignment
1.11.31.11.13.1	Root.Transition.GoodsShipment.Consignment.CountryOfRoutingOfConsignment.SequenceNumber
1.11.31.11.13.2	Root.Transition.GoodsShipment.Consignment.CountryOfRoutingOfConsignment.Country
1.11.31.11.14	Root.Transition.GoodsShipment.Consignment.ActiveBorderTransportMeans
1.11.31.11.14.1	Root.Transition.GoodsShipment.Consignment.ActiveBorderTransportMeans.TypeOfIdentification
1.11.31.11.14.2	Root.Transition.GoodsShipment.Consignment.ActiveBorderTransportMeans.IdentificationNumber
1.11.31.11.14.3	Root.Transition.GoodsShipment.Consignment.ActiveBorderTransportMeans.Nationality
1.11.31.11.15	Root.Transition.GoodsShipment.Consignment.TransportDocument
1.11.31.11.15.1	Root.Transition.GoodsShipment.Consignment.TransportDocument.SequenceNumber
1.11.31.11.15.2	Root.Transition.GoodsShipment.Consignment.TransportDocument.TypeAndQualifier
1.11.31.11.15.3	Root.Transition.GoodsShipment.Consignment.TransportDocument.ReferenceNumber
1.11.31.11.16	Root.Transition.GoodsShipment.Consignment.PaymentMethodTransport
1.11.31.12	Root.Transition.GoodsShipment.GoodsItem
1.11.31.12.1	Root.Transition.GoodsShipment.GoodsItem.SequenceNumber
1.11.31.12.2	Root.Transition.GoodsShipment.GoodsItem.StatisticalValue
1.11.31.12.3	Root.Transition.GoodsShipment.GoodsItem.NatureOfTransaction
1.11.31.12.4	Root.Transition.GoodsShipment.GoodsItem.CountryOfExport
1.11.31.12.5	Root.Transition.GoodsShipment.GoodsItem.ReferenceNumberUCR
1.11.31.12.6	Root.Transition.GoodsShipment.GoodsItem.RegistrationNumberExternal
1.11.31.12.7	Root.Transition.GoodsShipment.GoodsItem.Authorisation
1.11.31.12.7.1	Root.Transition.GoodsShipment.GoodsItem.Authorisation.SequenceNumber

1.11.31.12.7.2	Root.Transition.GoodsShipment.GoodsItem.Authorisation.Type
1.11.31.12.7.3	Root.Transition.GoodsShipment.GoodsItem.Authorisation.ReferenceNumber
1.11.31.12.7.4	Root.Transition.GoodsShipment.GoodsItem.Authorisation.HolderOfAuthorisation
1.11.31.12.8	Root.Transition.GoodsShipment.GoodsItem.Procedure
1.11.31.12.9	Root.Transition.GoodsShipment.GoodsItem.Consignor
1.11.31.12.9.1	Root.Transition.GoodsShipment.GoodsItem.Consignor.Code
1.11.31.12.9.2	Root.Transition.GoodsShipment.GoodsItem.Consignor.IdentificationNumber
1.11.31.12.9.3	Root.Transition.GoodsShipment.GoodsItem.Consignor.SubsidiaryNumber
1.11.31.12.9.4	Root.Transition.GoodsShipment.GoodsItem.Consignor.Name
1.11.31.12.9.5	Root.Transition.GoodsShipment.GoodsItem.Consignor.Address
1.11.31.12.9.5.1	Root.Transition.GoodsShipment.GoodsItem.Consignor.Address.StreetAndNumber
1.11.31.12.9.5.2	Root.Transition.GoodsShipment.GoodsItem.Consignor.Address.Postcode
1.11.31.12.9.5.3	Root.Transition.GoodsShipment.GoodsItem.Consignor.Address.City
1.11.31.12.9.5.4	Root.Transition.GoodsShipment.GoodsItem.Consignor.Address.Country
1.11.31.12.10	Root.Transition.GoodsShipment.GoodsItem.Consignee
1.11.31.12.10.1	Root.Transition.GoodsShipment.GoodsItem.Consignee.Code
1.11.31.12.10.2	Root.Transition.GoodsShipment.GoodsItem.Consignee.IdentificationNumber
1.11.31.12.10.3	Root.Transition.GoodsShipment.GoodsItem.Consignee.SubsidiaryNumber
1.11.31.12.10.4	Root.Transition.GoodsShipment.GoodsItem.Consignee.Name
1.11.31.12.10.5	Root.Transition.GoodsShipment.GoodsItem.Consignee.Address
1.11.31.12.10.5.1	Root.Transition.GoodsShipment.GoodsItem.Consignee.Address.StreetAndNumber
1.11.31.12.10.5.2	Root.Transition.GoodsShipment.GoodsItem.Consignee.Address.Postcode
1.11.31.12.10.5.3	Root.Transition.GoodsShipment.GoodsItem.Consignee.Address.City
1.11.31.12.10.5.4	Root.Transition.GoodsShipment.GoodsItem.Consignee.Address.Country
1.11.31.12.11	Root.Transition.GoodsShipment.GoodsItem.AdditionalSupplyChainActor
1.11.31.12.11.1	Root.Transition.GoodsShipment.GoodsItem.AdditionalSupplyChainActor.SequenceNumber
1.11.31.12.11.2	Root.Transition.GoodsShipment.GoodsItem.AdditionalSupplyChainActor.Role
1.11.31.12.11.3	Root.Transition.GoodsShipment.GoodsItem.AdditionalSupplyChainActor.Code
1.11.31.12.11.4	Root.Transition.GoodsShipment.GoodsItem.AdditionalSupplyChainActor.IdentificationNumber
1.11.31.12.12	Root.Transition.GoodsShipment.GoodsItem.CountryOfOrigin
1.11.31.12.13	Root.Transition.GoodsShipment.GoodsItem.RegionOfDispatch
1.11.31.12.14	Root.Transition.GoodsShipment.GoodsItem.DescriptionOfGoods
1.11.31.12.15	Root.Transition.GoodsShipment.GoodsItem.CusCode
1.11.31.12.16	Root.Transition.GoodsShipment.GoodsItem.CommodityCode
1.11.31.12.17	Root.Transition.GoodsShipment.GoodsItem.TARICAdditionalCode
1.11.31.12.17.1	Root.Transition.GoodsShipment.GoodsItem.TARICAdditionalCode.SequenceNumber
1.11.31.12.17.2	Root.Transition.GoodsShipment.GoodsItem.TARICAdditionalCode.TaricAdditionalCode
1.11.31.12.18	Root.Transition.GoodsShipment.GoodsItem.DangerousGoods
1.11.31.12.18.1	Root.Transition.GoodsShipment.GoodsItem.DangerousGoods.SequenceNumber
1.11.31.12.18.2	Root.Transition.GoodsShipment.GoodsItem.DangerousGoods.UNNumber
1.11.31.12.19	Root.Transition.GoodsShipment.GoodsItem.GrossMass
1.11.31.12.20	Root.Transition.GoodsShipment.GoodsItem.NetMass
1.11.31.12.21	Root.Transition.GoodsShipment.GoodsItem.SupplementaryUnits
1.11.31.12.22	Root.Transition.GoodsShipment.GoodsItem.Packaging
1.11.31.12.22.1	Root.Transition.GoodsShipment.GoodsItem.Packaging.SequenceNumber
1.11.31.12.22.2	Root.Transition.GoodsShipment.GoodsItem.Packaging.TypeOfPackages
1.11.31.12.22.3	Root.Transition.GoodsShipment.GoodsItem.Packaging.NumberOfPackages
1.11.31.12.22.4	Root.Transition.GoodsShipment.GoodsItem.Packaging.ShippingMarks
1.11.31.12.22.5	Root.Transition.GoodsShipment.GoodsItem.Packaging.PackageReference
1.11.31.12.23	Root.Transition.GoodsShipment.GoodsItem.PreviousDocument
1.11.31.12.23.1	Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.SequenceNumber
1.11.31.12.23.2	Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.TypeAndQualifier
1.11.31.12.23.3	Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.ReferenceNumber
1.11.31.12.23.4	Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.GoodsItemNumber
1.11.31.12.23.5	Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.MeasurementUnitAndQualifier
1.11.31.12.23.6	Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.Quantity
1.11.31.12.23.7	Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.ComplementOfInformation
1.11.31.12.24	Root.Transition.GoodsShipment.GoodsItem.SupportingDocument
1.11.31.12.24.1	Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.SequenceNumber
1.11.31.12.24.2	Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.TypeAndQualifier
1.11.31.12.24.3	Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.ReferenceNumber

1.11.31.12.24.4	Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.DocumentLineNumber
1.11.31.12.24.5	Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.ComplementOfInformation
1.11.31.12.24.6	Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.Detail
1.11.31.12.24.7	Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.IssuingAuthorityName
1.11.31.12.24.8	Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.IssuingDate
1.11.31.12.24.9	Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.ValidityDate
1.11.31.12.24.10	Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.MeasurementUnitAndQualifier
1.11.31.12.24.11	Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.ComplementaryUnit
1.11.31.12.24.12	Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.Quantity
1.11.31.12.24.13	Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.Currency
1.11.31.12.24.14	Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.Amount
1.11.31.12.25	Root.Transition.GoodsShipment.GoodsItem.AdditionalReference
1.11.31.12.25.1	Root.Transition.GoodsShipment.GoodsItem.AdditionalReference.SequenceNumber
1.11.31.12.25.2	Root.Transition.GoodsShipment.GoodsItem.AdditionalReference.TypeAndQualifier
1.11.31.12.25.3	Root.Transition.GoodsShipment.GoodsItem.AdditionalReference.ReferenceNumber
1.11.31.12.25.4	Root.Transition.GoodsShipment.GoodsItem.AdditionalReference.Detail
1.11.31.12.25.5	Root.Transition.GoodsShipment.GoodsItem.AdditionalReference.Currency
1.11.31.12.25.6	Root.Transition.GoodsShipment.GoodsItem.AdditionalReference.Amount
1.11.31.12.26	Root.Transition.GoodsShipment.GoodsItem.AdditionalInformation
1.11.31.12.26.1	Root.Transition.GoodsShipment.GoodsItem.AdditionalInformation.SequenceNumber
1.11.31.12.26.2	Root.Transition.GoodsShipment.GoodsItem.AdditionalInformation.Code
1.11.31.12.26.3	Root.Transition.GoodsShipment.GoodsItem.AdditionalInformation.Text
1.11.31.12.27	Root.Transition.GoodsShipment.GoodsItem.PaymentMethodTransport
1.11.31.12.28	Root.Transition.GoodsShipment.GoodsItem.OutwardProcessing
1.11.31.12.28.1	Root.Transition.GoodsShipment.GoodsItem.OutwardProcessing.Replacement
1.11.31.12.28.2	Root.Transition.GoodsShipment.GoodsItem.OutwardProcessing.ReimportDate
1.11.31.12.29	Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing
1.11.31.12.29.1	Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.LRN
1.11.31.12.29.2	Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.Authorisation
1.11.31.12.29.2.1	Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.Authorisation.Type
1.11.31.12.29.2.2	Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.Authorisation.ReferenceNumber
1.11.31.12.29.3	Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference
1.11.31.12.29.3.1	Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.SequenceNumber
1.11.31.12.29.3.2	Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.AccessViaATLAS
1.11.31.12.29.3.3	Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.MRN
1.11.31.12.29.3.4	Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.RegistrationNumber
1.11.31.12.29.3.5	Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.GoodsItemNumber
1.11.31.12.29.3.6	Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.UsualTreatment
1.11.31.12.29.3.7	Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.ComplementOfInformation
1.11.31.12.29.3.8	Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.CommodityCode
1.11.31.12.29.3.9	Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.GoodsReduction
1.11.31.12.29.3.9.1	Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.GoodsReduction.MeasurementUnitAndQualifier
1.11.31.12.29.3.9.2	Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.GoodsReduction.Quantity
1.11.31.12.29.3.10	Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.GoodsReductionAfterTreatment
1.11.31.12.29.3.10.1	Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.GoodsReductionAfterTreatment.MeasurementUnitAndQualifier
1.11.31.12.29.3.10.2	Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.GoodsReductionAfterTreatment.Quantity
1.11.31.12.30	Root.Transition.GoodsShipment.GoodsItem.InwardProcessing
1.11.31.12.30.1	Root.Transition.GoodsShipment.GoodsItem.InwardProcessing.SimplyGrantedAuthorisation
1.11.31.12.30.2	Root.Transition.GoodsShipment.GoodsItem.InwardProcessing.Authorisation
1.11.31.12.30.2.1	Root.Transition.GoodsShipment.GoodsItem.InwardProcessing.Authorisation.Type
1.11.31.12.30.2.2	Root.Transition.GoodsShipment.GoodsItem.InwardProcessing.Authorisation.ReferenceNumber
1.11.31.12.30.3	Root.Transition.GoodsShipment.GoodsItem.InwardProcessing.CustomsOfficeOfSupervision
1.11.31.12.30.4	Root.Transition.GoodsShipment.GoodsItem.InwardProcessing.GoodsReference
1.11.31.12.30.4.1	Root.Transition.GoodsShipment.GoodsItem.InwardProcessing.GoodsReference.SequenceNumber
1.11.31.12.30.4.2	Root.Transition.GoodsShipment.GoodsItem.InwardProcessing.GoodsReference.AccessViaATLAS
1.11.31.12.30.4.3	Root.Transition.GoodsShipment.GoodsItem.InwardProcessing.GoodsReference.MRN
1.11.31.12.30.4.4	Root.Transition.GoodsShipment.GoodsItem.InwardProcessing.GoodsReference.RegistrationNumber
1.11.31.12.30.4.5	Root.Transition.GoodsShipment.GoodsItem.InwardProcessing.GoodsReference.GoodsItemNumber
1.11.31.12.30.4.6	Root.Transition.GoodsShipment.GoodsItem.InwardProcessing.GoodsReference.GoodsRelatedData



1.11.31.12.31	Root.Transition.GoodsShipment.GoodsItem.AdditionalId
1.11.31.12.32	Root.Transition.GoodsShipment.GoodsItem.QuantityOfGoods
1.11.31.12.33	Root.Transition.GoodsShipment.GoodsItem.QuantityOfGoodsMeasurement
1.11.31.12.34	Root.Transition.GoodsShipment.GoodsItem.ArticleNumber
1.11.31.12.35	Root.Transition.GoodsShipment.GoodsItem.TransportCosts
1.11.31.12.36	Root.Transition.GoodsShipment.GoodsItem.TransportCostsCurrency
1.11.31.12.37	Root.Transition.GoodsShipment.GoodsItem.InvoiceAmount
1.11.31.12.38	Root.Transition.GoodsShipment.GoodsItem.InvoiceCurrency



Identifier		Required/ Optional	Format	Iteration
1 Root		K		1 - 1
1.1 Root.Client		K	..8	1 - 1
Client				
Identifier of the client where the operation is processed in AC.				
1.2 Root.User		O	..35	0 - 1
User				
AC-user under whose name the declaration is being imported and may be send to customs.				
1.3 Root.CountryOfLodgement		K	2	1 - 1
Country of lodgement				
ISO code of the country in which the operation is registered.				
Permitted values:				
DE		This import Interface may only be used for country of lodgement 'DE'		
1.4 Root.OperationDomain		K	..35	1 - 1
Operation domain				
Identifier for the process of the operation in AC. The country of lodgement, the operation domain and the operation type classify it.				
Permitted values:				
AES		Operation domain 'AES'		
1.5 Root.OperationType		K	..50	1 - 1
Operation type				
Identifier for the operation.				
Permitted values:				
Anmeldung zur Ausfuhr		Operation type 'Anmeldung zur Ausfuhr'		
1.6 Root.ID		O	..	0 - 1
ID				
For updating processes: ID is the transaction number created by AC after a transaction is registered. If the declaration is to be updated via the interface by ID, the field is allowed to be sent.				
1.7 Root.ReferenceNumber		O	..50	0 - 1
Reference number				
The reference number is the internal reference number of the declaration.				
This number needs to be unique for all processes of the same classification (Combination of country of lodgement, operation domain and operation type).				
1.8 Root.AdditionalReferenceNumber		O	..50	0 - 1
Additional reference number				
An additional reference number that can be used for the technical identification of the transaction. (not mandatory)				
1.9 Root.StatusNotificationEmail		O	..255	0 - 1
Status notification				
Use of the e-mail function in Advantage Customs is required. An email address is provided that is used for status notifications for the customs declaration. The configured e-mail settings in Advantage Customs are considered.				
1.10 Root.Meta		K		1 - 1
Meta				
The following elements define the processing of the transaction.				
1.10.1 Root.Meta.Operation		K	..	1 - 1
Operation				
Specification of the processing in AC.				
Permitted values:				
0		simulation of an import including validation (nothing will be stored in AC)		
1		import of the operation into AC without business validation and dispatch		
5		import of the operation into AC including business validation and dispatch (in case of validation errors the operation will still be stored in AC)		
7		import of the operation into AC including business validation and dispatch (in case of validation errors the operation will NOT be stored in AC)		

Identifier		Required/Optional	Format	Iteration
<b>1.10.2 Root.Meta.ReferenceType</b>		0	..35	0 - 1
Reference type				
For updating processes: The reference type controls the update logic of the interface: If the element 'Root/ReferenceType' is not transmitted in the data set, it is always a new creation. If a reference type is transmitted, it is an update data set. The specified value controls which reference is used to determine the transaction to be updated in AC.				
Permitted values:				
ID	ID Referencing via the unique technical ID of the transaction. The ID is assigned by AC when a new transaction is created. In order to control updates from the customer's system via this ID, the system must receive and save the ID (e.g. via receipt or export interfaces).			
ReferenceNumber	Reference number Referencing via the reference number of the transaction.			
<b>1.10.3 Root.Meta.CopyTemplate</b>		0		0 - 1
CopyTemplate				
The following elements define the references for copytemplates.				
<b>1.10.3.1 Root.Meta.CopyTemplate.Reference</b>		K	..50	1 - 1
Reference				
If contents are to be taken over from an AC copy template, the reference number of the copy template is indicated here.				
<b>1.10.3.2 Root.Meta.CopyTemplate.ReferenceType</b>		K	..35	1 - 1
Reference type				
The ID or ReferenceNumber must be entered as the Reference Type for the copy template.				
Permitted values:				
ID	ID Referencing via the unique technical ID of the transaction. The ID is assigned by AC when a new transaction is created.			
ReferenceNumber	Reference number Referencing via the reference number of the transaction.			
<b>1.10.4 Root.Meta.ShipmentNumber</b>		0	..35	0 - 1
If a shipment number ist provided, a shipment (Sendung) will be created together with export data. If this shipment number already exists, this process will become the follow-up process for this shipment.				
<b>1.10.5 Root.Meta.PreventFloodingArticleData</b>		0		0 - 1
The field controls whether article master data is retrieved based on the provided article number.				
By default, the system retrieves the article master data automatically. If the indicator "true" is submitted in this field, the system does not retrieve article master data. Instead, the values provided in the interface are used as transmitted. If the indicator "false" or no field at all is submitted, the system uses the article number to retrieve and apply the corresponding article master data.				
<b>1.10.6 Root.Meta.TransferAuthorisationFromMasterData</b>		0		0 - 1
Transfer authorisation number from master data				
If the indicator "true" is submitted in this field, the authorisation number is identified on the basis of the business partner. Otherwise, the authorisation number must be submitted in the XML file.				
<b>1.10.7 Root.Meta.PerformUserDefinedActions</b>		0		0 - 1
Perform user defined actions				
If the indicator "true" is submitted in this field, user defined actions are performed as declared for the kind of business process. If the indicator is left out, user defined actions are performed only if declared in the configuration of the import interface. If the indicator "false" is submitted in this field, no user defined actions are performed regardless of the import interface configuration.				
<b>1.10.8 Root.Meta.AllocationNetMass</b>		0		0 - 1
To calculate the statistical value, the allocation by net weight can be used. You must choose between allocation by net mass and allocation by invoice amount. The information is not transmitted to ATLAS.				
<b>1.10.9 Root.Meta.AllocationInvoiceAmount</b>		0		0 - 1
To calculate the statistical value, the allocation by invoice amount can be used. You must choose between allocation by net mass and allocation by invoice amount. The information is not transmitted to ATLAS.				
<b>1.10.10 Root.Meta.PositionReference</b>		0		0 - 999
Position reference				
<b>1.10.10.1 Root.Meta.PositionReference.DeclarationGoodsItemNumber</b>		K	n....5	1 - 1
The corresponding position is to be transferred.				
<b>1.10.10.2 Root.Meta.PositionReference.CalculateStatisticalValue</b>		0		0 - 1
The calculation of the statistical value from the transport costs and the invoice price can be initiated via this action.				
<b>1.10.10.3 Root.Meta.PositionReference.StockSelection</b>		0		0 - 1
By specifying the following data fields, a stock account can be determined for a procedure transfer.				

Identifier	Required/Optional	Format	Iteration
<b>1.10.10.3.1 Root.Meta.PositionReference.StockSelection.RegistrationID</b>	0	..27	0 - 1
The MRN or ATLAS registration number with item number is provided for the registration ID. If this information is provided, no further fields are to be transmitted for stock selection. Only the procedure code (StorageProcedureCode) is permitted.  Format: MRN/item number or ATLAS registration number/item number  Example: 25DE5866BCMO0053R7/1			
<b>1.10.10.3.2 Root.Meta.PositionReference.StockSelection.WarehouseAccountNumber</b>	0	..40	0 - 1
The corresponding warehouse stock can be assigned via the warehouse stock account number.			
<b>1.10.10.3.3 Root.Meta.PositionReference.StockSelection.LvsID</b>	0	..20	0 - 1
The LVS ID can be used as a reference from AC to determine the warehouse stock account.			
<b>1.10.10.3.4 Root.Meta.PositionReference.StockSelection.DisposerWarehouse</b>	0	..20	0 - 1
To determine the stock account, the disposer for the warehouse can be used as a filter.			
<b>1.10.10.3.5 Root.Meta.PositionReference.StockSelection.ArticleNumber</b>	0	..30	0 - 1
The article number of the warehouse stock can be used to determine the warehouse stock account.			
<b>1.10.10.3.6 Root.Meta.PositionReference.StockSelection.StorageProcedureCode</b>	K	..	1 - 1
Permitted values:			
71      The customs procedure must be indicated.			
<b>1.10.10.3.7 Root.Meta.PositionReference.StockSelection.StorageLocationCode</b>	0	..100	0 - 1
The storage location can be used as a filter to determine the stock account.			
<b>1.10.10.3.8 Root.Meta.PositionReference.StockSelection.AuthorisationReferenceNumber</b>	0	..35	0 - 1
The authorization number from the warehouse must be indicated.			
<b>1.10.10.3.9 Root.Meta.PositionReference.StockSelection.AdditionalReferenceNumber</b>	0	..100	0 - 1
The additional reference number from the warehouse must be indicated.			
<b>1.11 Root.Transition</b>	K		1 - 1
Transition  Field which AC internally uses to identify the current type of transition. Usually it correlates to the type/name of the exchanged message.			
<b>1.11.1 Root.Transition.TransitionType</b>	K	9	1 - 1
Transition type  Indication of the ATLAS message.  Permitted values:			
E_EXP_DAT      The ATLAS message type must always be E_EXP_DAT.			
<b>1.11.2 Root.Transition.LRN</b>	0	..22	0 - 1
LRN  The local reference number is the reference number of the transit declaration. The LRN is assigned as a unique reference by the creator of the transit declaration.			
<b>1.11.3 Root.Transition.DeclarationType</b>	0	..5	0 - 1
Type of declaration  ATLAS code list: C0231  A type of export operation must be indicated			
<b>1.11.4 Root.Transition.ExportDeclarationType</b>	0	..	0 - 1
Type of export declaration  ATLAS code list: A0121  Type of declaration for the export procedure with clarifications and, if applicable, use of simplifications.			
<b>1.11.5 Root.Transition.PartyConstellation</b>	0	..	0 - 1
Constellation of participants  ATLAS code list: A0127  The participant constellation represents the relationships between exporter , declarant and message creator in the various possibilities of agency and subcontractor relationships.			
<b>1.11.6 Root.Transition.DeclarationSubmissionDateAndTime</b>	0	..	0 - 1
Declaration submission date and time  Date and time of submission			

Identifier	Required/Optional	Format	Iteration
<b>1.11.7 Root.Transition.DeclarationSubmissionTimezone</b>	0	..255	0 - 1
Indication of the time zone.  IANA standard ( <a href="https://www.iana.org/time-zones">https://www.iana.org/time-zones</a> )			
<b>1.11.8 Root.Transition.DecisiveDate</b>	0	..	0 - 1
Decisive date  Relevant date for the subsequent export declaration.			
<b>1.11.9 Root.Transition.ExitDate</b>	0	..	0 - 1
Exit date  Date of physical exit of the goods from the customs territory of the European Union.  Note: The specification of the data field is required and only allowed if the data field 'Type of export declaration' is specified with one of the values '10-0----', '11000000', '12000000' or '13000000'.			
<b>1.11.10 Root.Transition.PresentationStartDateAndTime</b>	0	..	0 - 1
Presentation of the goods date and time  Start of the planned period for presentation and/or packing and loading.  Note: The indication of the data field is required if the data field 'Type of export declaration' is indicated with one of the values '-----2--' (declaration with application for presentation outside the official place of business according to Section 12(4) AWW).			
<b>1.11.11 Root.Transition.PresentationStartTimezone</b>	0	..255	0 - 1
Indication of the time zone.  IANA standard ( <a href="https://www.iana.org/time-zones">https://www.iana.org/time-zones</a> )			
<b>1.11.12 Root.Transition.LoadingEndDateAndTime</b>	0	..	0 - 1
Loading of the goods date and time  End of the planned period for presentation and/or packing and loading.  Note: The indication of the data field is required if the data field 'Type of export declaration' is indicated with one of the values '-----2--' (declaration with application for presentation outside the official place of business according to Section 12(4) AWW).			
<b>1.11.13 Root.Transition.LoadingEndTimezone</b>	0	..255	0 - 1
Indication of the time zone.  IANA standard ( <a href="https://www.iana.org/time-zones">https://www.iana.org/time-zones</a> )			
<b>1.11.14 Root.Transition.Security</b>	0	..	0 - 1
Guarantee  ATLAS code list: C0217  Indicator for the declaration of the data for the exit summary declaration.  Note: Only the value "0" is allowed if the data field "Type of declaration" is specified with the value "CO".			
<b>1.11.15 Root.Transition.SpecificCircumstanceIndicator</b>	0	3	0 - 1
Indicator of specific circumstances  ATLAS code list: A0296  Indicator of specific circumstance			
<b>1.11.16 Root.Transition.TransportCosts</b>	0	n....15,2	0 - 1
The transport costs is used in combination with the allocation to calculate the statistical value. The transport costs are not transferred to ATLAS.			
<b>1.11.17 Root.Transition.TransportCostsCurrency</b>	0	3	0 - 1
The currency belongs to the transport costs. The information is not transmitted to ATLAS.			
<b>1.11.18 Root.Transition.TotalAmountInvoiced</b>	0	n....16,2	0 - 1
Invoiced amount of all goods  Note: In the case of free delivery, enter an invoiced amount of "0".			
<b>1.11.19 Root.Transition.InvoiceCurrency</b>	0	3	0 - 1
Invoice currency  ATLAS code list: C0352  Currency for total amount			

Identifier	Required/Optional	Format	Iteration
<b>1.11.20 Root.Transition.Authorisation</b>	0		0 - 9
Authorisation Authorisation granted by the customs authorities.			
<b>1.11.20.1 Root.Transition.Authorisation.SequenceNumber</b>	0	n....1	0 - 1
Sequence number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
<b>1.11.20.2 Root.Transition.Authorisation.Type</b>	0	4	0 - 1
Type ATLAS code list: S0605 Type of authorisation			
<b>1.11.20.3 Root.Transition.Authorisation.ReferenceNumber</b>	0	..35	0 - 1
Reference number Authorisation number			
<b>1.11.21 Root.Transition.CustomsOfficeOfPresentation</b>	0	8	0 - 1
Customs office of presentation ATLAS code list: C0193 Office in another Member State where the goods are available for customs controls at a place authorised in the CCL export authorisation.			
<b>1.11.22 Root.Transition.CustomsOfficeOfExport</b>	0	8	0 - 1
Customs office of export ATLAS code list: D0293 Indication of the responsible customs office of export			
<b>1.11.23 Root.Transition.CustomsOfficeOfSupplement</b>	0	8	0 - 1
Customs office of supplement ATLAS code list: D0193 Indication of the customs office which is responsible for the supplementary declaration. Note: The specification of the data is required and only permitted if the data field 'Export declaration type' is specified with one of the values „■■■■■1■' (incomplete declaration)			
<b>1.11.24 Root.Transition.CustomsOfficeOfExitDeclared</b>	0	8	0 - 1
Customs office of exit (declared) ATLAS code list: C0294 Indication of the customs office of exit (declared). Note: The entry is not required for subsequent declarations and monthly collective declarations, as no further monitoring of the actual exit will take place. Instead, the declaration of the data group 'Actual customs office of exit' is usually required.			
<b>1.11.25 Root.Transition.CustomsOfficeOfExitActual</b>	0	8	0 - 1
Customs office of exit (actual) ATLAS code list: C0194 Actual customs office of exit Note: The indication of the data group is required and only allowed if the data field "Type of export declaration" is indicated with one of the values "10-0----", "11000000", "12000000" or "13000000".			
<b>1.11.26 Root.Transition.ContractualPartner</b>	0		0 - 1
Contractual partner			
<b>1.11.26.1 Root.Transition.ContractualPartner.Code</b>	0	..250	0 - 1
Code The reference code for the business partner master data in AC.			
<b>1.11.26.2 Root.Transition.ContractualPartner.IdentificationNumber</b>	0	..17	0 - 1
Identification number Identification number / EORI number			

Identifier	Required/Optional	Format	Iteration
<b>1.11.26.3 Root.Transition.ContractualPartner.SubsidiaryNumber</b>	0	..	0 - 1
Subsidiary number  Number of the subsidiary of the contracutal partner, assigned by the German customs authority.			
<b>1.11.26.4 Root.Transition.ContractualPartner.Name</b>	0	..70	0 - 1
Name or company name of the contractual partner.  Note: The indication of the data field is required and only permissible if the data field 'Identification number' is not indicated.			
<b>1.11.26.5 Root.Transition.ContractualPartner.Address</b>	0		0 - 1
Address data			
<b>1.11.26.5.1 Root.Transition.ContractualPartner.Address.StreetAndNumber</b>	0	..70	0 - 1
Street and number			
<b>1.11.26.5.2 Root.Transition.ContractualPartner.Address.Postcode</b>	0	..17	0 - 1
postcode			
<b>1.11.26.5.3 Root.Transition.ContractualPartner.Address.City</b>	0	..35	0 - 1
city			
<b>1.11.26.5.4 Root.Transition.ContractualPartner.Address.Country</b>	0	2	0 - 1
Country  ATLAS code list: C0248  Country code			
<b>1.11.27 Root.Transition.Exporter</b>	0		0 - 1
Exporter  Customs exporter  Note: The indication of the data group is required and only allowed if the data field "constellation of participants" is indicated with one of the values "-1-" (exporter can be indirectly represented).			
<b>1.11.27.1 Root.Transition.Exporter.Code</b>	0	..250	0 - 1
Code  The reference code for the business partner master data in AC.			
<b>1.11.27.2 Root.Transition.Exporter.IdentificationNumber</b>	0	..17	0 - 1
Identification number  Indentification number / EORI number			
<b>1.11.27.3 Root.Transition.Exporter.SubsidiaryNumber</b>	0	..	0 - 1
Subsidiary number  Number of the subsidiary of the exporter, assigned by the German customs authority.			
<b>1.11.27.4 Root.Transition.Exporter.Name</b>	0	..70	0 - 1
Name  Name or company name of the exporter.  Note: The indication of the data field is required and only permissible if the data field "Identification number" is not indicated.			
<b>1.11.27.5 Root.Transition.Exporter.Address</b>	0		0 - 1
Address data of the exporter  Note: The indication of the data group is required and only permissible if the data field "Identification number" is not indicated.			
<b>1.11.27.5.1 Root.Transition.Exporter.Address.StreetAndNumber</b>	0	..70	0 - 1
Street and number			
<b>1.11.27.5.2 Root.Transition.Exporter.Address.Postcode</b>	0	..17	0 - 1
Postcode			
<b>1.11.27.5.3 Root.Transition.Exporter.Address.City</b>	0	..35	0 - 1
City			
<b>1.11.27.5.4 Root.Transition.Exporter.Address.Country</b>	0	2	0 - 1
Country  ATLAS code list: C0248  Country code of exporter			

Identifier	Required/Optional	Format	Iteration
<b>1.11.28 Root.Transition.Declarant</b>	0		0 - 1
Declarant			
<b>1.11.28.1 Root.Transition.Declarant.Code</b>	0	..250	0 - 1
Code			
The reference code for the business partner master data in AC.			
<b>1.11.28.2 Root.Transition.Declarant.IdentificationNumber</b>	0	..17	0 - 1
Identification number			
Indentification number / EORI number			
<b>1.11.28.3 Root.Transition.Declarant.SubsidiaryNumber</b>	0	..	0 - 1
Subsidiary number			
Number of the subsidiary of the declarant assigned by the German customs authority.			
<b>1.11.28.4 Root.Transition.Declarant.Name</b>	0	..70	0 - 1
Name			
Name or company name of the declarant			
Note: The indication of the data field is required and only permissible if the data field "Identification number" is not indicated.			
<b>1.11.28.5 Root.Transition.Declarant.Address</b>	0		0 - 1
Address data of the declarant			
Note: The indication of the data group is required and only permissible if the data field "Identification number" is not indicated.			
<b>1.11.28.5.1 Root.Transition.Declarant.Address.StreetAndNumber</b>	0	..70	0 - 1
Street and number			
<b>1.11.28.5.2 Root.Transition.Declarant.Address.Postcode</b>	0	..17	0 - 1
Postcode			
<b>1.11.28.5.3 Root.Transition.Declarant.Address.City</b>	0	..35	0 - 1
City			
<b>1.11.28.5.4 Root.Transition.Declarant.Address.Country</b>	0	2	0 - 1
Country			
ATLAS code list: C0248			
Country code of exporter			
<b>1.11.28.6 Root.Transition.Declarant.ContactPerson</b>	0		0 - 1
Contact person			
Contact person of declarant			
Note: The specification of the data group is also recommended in the case of a direct representation in order to simplify possible consultations.			
<b>1.11.28.6.1 Root.Transition.Declarant.ContactPerson.Name</b>	0	..70	0 - 1
Name of the contact person			
<b>1.11.28.6.2 Root.Transition.Declarant.ContactPerson.PhoneNumber</b>	0	..35	0 - 1
Phone number of the cpmtact person			
<b>1.11.28.6.3 Root.Transition.Declarant.ContactPerson.EMailAddress</b>	0	..256	0 - 1
E-mail address of the contact person			
<b>1.11.29 Root.Transition.Representative</b>	0		0 - 1
Representative			
Representative of declarant			
Note: The indication of the data group is required and only permissible if the data field "Constellation of participants" is indicated with one of the values "--1-" (Declarant can be represented directly).			
<b>1.11.29.1 Root.Transition.Representative.Code</b>	0	..250	0 - 1
Code			
The reference code for the business partner master data in AC.			
<b>1.11.29.2 Root.Transition.Representative.IdentificationNumber</b>	0	..17	0 - 1
Identification number			
Indentification number / EORI number			



Identifier	Required/Optional	Format	Iteration
<b>1.11.29.3 Root.Transition.Representative.SubsidiaryNumber</b>	0	..	0 - 1
Subsidiary number  Number of the subsidiary of the representative assigned by the German customs authority.			
<b>1.11.29.4 Root.Transition.Representative.ContactPerson</b>	0		0 - 1
Contact person of representative			
<b>1.11.29.4.1 Root.Transition.Representative.ContactPerson.Name</b>	0	..70	0 - 1
Name of the contact person			
<b>1.11.29.4.2 Root.Transition.Representative.ContactPerson.PhoneNumber</b>	0	..35	0 - 1
phone number			
<b>1.11.29.4.3 Root.Transition.Representative.ContactPerson.EMailAddress</b>	0	..256	0 - 1
E-mail address			
<b>1.11.30 Root.Transition.SubContractor</b>	0		0 - 1
Sub-contractor  Sub-contractor of exporter  Note: The indication of the data group is required and only allowed if the data field "constellation of participants" is indicated with one of the values "---1" (Exporter instructs subcontractor).			
<b>1.11.30.1 Root.Transition.SubContractor.Code</b>	0	..250	0 - 1
Code  The reference code for the business partner master data in AC.			
<b>1.11.30.2 Root.Transition.SubContractor.IdentificationNumber</b>	0	..17	0 - 1
Identification number  Indentification number / EORI number			
<b>1.11.30.3 Root.Transition.SubContractor.SubsidiaryNumber</b>	0	..	0 - 1
Subsidiary number  Number of the subsidiary of the sub-contractor assigned by the German customs authority.			
<b>1.11.30.4 Root.Transition.SubContractor.Name</b>	0	..70	0 - 1
Name  Name or company name of the sub-contractor.  Note: The indication of the data field is required and only permissible if the data field "Identification number" is not indicated.			
<b>1.11.30.5 Root.Transition.SubContractor.Address</b>	0		0 - 1
Address  Address data of the sub-contractor  Note: The indication of the data group is required and only permissible if the data field "Identification number" is not indicated.			
<b>1.11.30.5.1 Root.Transition.SubContractor.Address.StreetAndNumber</b>	0	..70	0 - 1
Street and number			
<b>1.11.30.5.2 Root.Transition.SubContractor.Address.Postcode</b>	0	..17	0 - 1
postcode			
<b>1.11.30.5.3 Root.Transition.SubContractor.Address.City</b>	0	..35	0 - 1
city			
<b>1.11.30.5.4 Root.Transition.SubContractor.Address.Country</b>	0	2	0 - 1
country  ATLAS code list: C0248  Country code of exporter			
<b>1.11.31 Root.Transition.GoodsShipment</b>	0		0 - 1
Goods shipment			
<b>1.11.31.1 Root.Transition.GoodsShipment.NatureOfTransaction</b>	0	..	0 - 1
Nature of transaction  In this data field, the type of transaction (information from which certain clauses of the business contract become apparent) is to be indicated with the key number accordingly.			

Identifier	Required/Optional	Format	Iteration
<b>1.11.31.2 Root.Transition.GoodsShipment.CountryOfExport</b>	0	2	0 - 1
Country of export ATLAS code list: C0010 Country of export			
<b>1.11.31.3 Root.Transition.GoodsShipment.CountryOfDestination</b>	0	2	0 - 1
Country of destination ATLAS code list: C0008 Country of destination			
<b>1.11.31.4 Root.Transition.GoodsShipment.AdditionalSupplyChainActor</b>	0		0 - 99
Additional supply chain actor  Economic operator of a third country in the context of a trade partnership programme developed in accordance with the World Customs Organisation's Framework of Standards for Securing and Facilitating Global Trade, as recognised by the European Union			
<b>1.11.31.4.1 Root.Transition.GoodsShipment.AdditionalSupplyChainActor.SequenceNumber</b>	0	n....2	0 - 1
Sequence number  The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
<b>1.11.31.4.2 Root.Transition.GoodsShipment.AdditionalSupplyChainActor.Role</b>	0	..3	0 - 1
Role ATLAS code list: C0704 Role of additional supply chain actor			
<b>1.11.31.4.3 Root.Transition.GoodsShipment.AdditionalSupplyChainActor.Code</b>	0	..250	0 - 1
Code  The reference code for the business partner master data in AC.			
<b>1.11.31.4.4 Root.Transition.GoodsShipment.AdditionalSupplyChainActor.IdentificationNumber</b>	0	..17	0 - 1
Identification number  Indentification number / EORI number			
<b>1.11.31.5 Root.Transition.GoodsShipment.DeliveryTerms</b>	0		0 - 1
Delivery terms  Clauses of the business contract with details of the delivery terms.			
<b>1.11.31.5.1 Root.Transition.GoodsShipment.DeliveryTerms.IncotermsCode</b>	0	3	0 - 1
Incoterms-code ATLAS code list: C0090 Incoterms code			
<b>1.11.31.5.2 Root.Transition.GoodsShipment.DeliveryTerms.UNLocode</b>	0	..17	0 - 1
UN/LOCODE ATLAS code list: C0244 United Nations coding on location information for trade and transport			
<b>1.11.31.5.3 Root.Transition.GoodsShipment.DeliveryTerms.Location</b>	0	..35	0 - 1
Location  Location related to the delivery term			
<b>1.11.31.5.4 Root.Transition.GoodsShipment.DeliveryTerms.Country</b>	0	2	0 - 1
Country ATLAS code list: C0248 Country code  Note: The specification of the data field is required if the data field "INCOTERMS code" is specified with a value not equal to "XXX", but not the data field "UN/LOCODE".			

Identifier	Required/Optional	Format	Iteration
<b>1.11.31.5.5 Root.Transition.GoodsShipment.DeliveryTerms.Text</b>	0	..512	0 - 1
Text Description of delivery term  Note: The specification of the data field is required and only allowed if the data field "INCOTERMS code" is specified with the value "XXX".			
<b>1.11.31.6 Root.Transition.GoodsShipment.OutwardProcessing</b>	0		0 - 1
Outward processing  Note: The indication of the data group is required and only allowed if the data field "Type of export declaration" is indicated with one of the values "--1-----" (customs outward processing).			
<b>1.11.31.6.1 Root.Transition.GoodsShipment.OutwardProcessing.Reimport</b>	0		0 - 99
Re-import Proposed re-importation of compensating products			
<b>1.11.31.6.1.1 Root.Transition.GoodsShipment.OutwardProcessing.Reimport.SequenceNumber</b>	0	n....2	0 - 1
Sequence number  The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
<b>1.11.31.6.1.2 Root.Transition.GoodsShipment.OutwardProcessing.Reimport.Country</b>	0	2	0 - 1
Country ATLAS code list: IO809 Country code			
<b>1.11.31.6.2 Root.Transition.GoodsShipment.OutwardProcessing.IdentificationMeans</b>	0		0 - 7
Identification means			
<b>1.11.31.6.2.1 Root.Transition.GoodsShipment.OutwardProcessing.IdentificationMeans.SequenceNumber</b>	0	n....1	0 - 1
Sequence number  The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
<b>1.11.31.6.2.2 Root.Transition.GoodsShipment.OutwardProcessing.IdentificationMeans.Type</b>	0	1	0 - 1
Type ATLAS code list: AO160 Type of means of identification			
<b>1.11.31.6.2.3 Root.Transition.GoodsShipment.OutwardProcessing.IdentificationMeans.Description</b>	0	..350	0 - 1
Description Description of the identification means			
<b>1.11.31.6.3 Root.Transition.GoodsShipment.OutwardProcessing.Product</b>	0		0 - 999
product  The compensating products must, in the absence of a formal authorisation, be identified in advance by a commodity code and a description of the goods.			
<b>1.11.31.6.3.1 Root.Transition.GoodsShipment.OutwardProcessing.Product.SequenceNumber</b>	0	n....3	0 - 1
Sequence number  The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
<b>1.11.31.6.3.2 Root.Transition.GoodsShipment.OutwardProcessing.Product.DescriptionOfGoods</b>	0	..512	0 - 1
Description of goods			
<b>1.11.31.6.3.3 Root.Transition.GoodsShipment.OutwardProcessing.Product.CommodityCode</b>	0	..	0 - 1
Commodity code			
<b>1.11.31.7 Root.Transition.GoodsShipment.PreviousDocument</b>	0		0 - 99
Previous documents Details of previous document			
<b>1.11.31.7.1 Root.Transition.GoodsShipment.PreviousDocument.SequenceNumber</b>	0	n....2	0 - 1
Sequence number  The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			

Identifier	Required/Optional	Format	Iteration
<b>1.11.31.7.2 Root.Transition.GoodsShipment.PreviousDocument.TypeAndQualifier</b>	0	..8	0 - 1
Type and Qualifier ATLAS code list: IO931 Type and qualifier of the previous docuement			
<b>1.11.31.7.3 Root.Transition.GoodsShipment.PreviousDocument.ReferenceNumber</b>	0	..70	0 - 1
Reference number Reference number of previous documents			
<b>1.11.31.8 Root.Transition.GoodsShipment.SupportingDocument</b>	0		0 - 99
Supporting document			
<b>1.11.31.8.1 Root.Transition.GoodsShipment.SupportingDocument.SequenceNumber</b>	0	n....2	0 - 1
Sequence number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
<b>1.11.31.8.2 Root.Transition.GoodsShipment.SupportingDocument.TypeAndQualifier</b>	0	..8	0 - 1
Type and Qualifier ATLAS code list: IO921 Type and qualifier of the supporting document			
<b>1.11.31.8.3 Root.Transition.GoodsShipment.SupportingDocument.ReferenceNumber</b>	0	..70	0 - 1
Reference number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
<b>1.11.31.8.4 Root.Transition.GoodsShipment.SupportingDocument.DocumentLineItemNumber</b>	0	n....5	0 - 1
Document line number Reference to a numbered entry in the document.			
<b>1.11.31.8.5 Root.Transition.GoodsShipment.SupportingDocument.IssuingAuthorityName</b>	0	..70	0 - 1
Issuing authority name Authority that issued the document			
<b>1.11.31.8.6 Root.Transition.GoodsShipment.SupportingDocument.IssuingDate</b>	0	..	0 - 1
Issuing date Date on which the document was issued			
<b>1.11.31.8.7 Root.Transition.GoodsShipment.SupportingDocument.ValidityDate</b>	0	..	0 - 1
Validity date Date of the last validity of the document			
<b>1.11.31.9 Root.Transition.GoodsShipment.AdditionalReference</b>	0		0 - 99
Additional reference			
<b>1.11.31.9.1 Root.Transition.GoodsShipment.AdditionalReference.SequenceNumber</b>	0	n....2	0 - 1
Sequence number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
<b>1.11.31.9.2 Root.Transition.GoodsShipment.AdditionalReference.TypeAndQualifier</b>	0	..8	0 - 1
Type and qualifier ATLAS code list: IO911 Type and qualifier of the additional reference			
<b>1.11.31.9.3 Root.Transition.GoodsShipment.AdditionalReference.ReferenceNumber</b>	0	..70	0 - 1
Reference number Additional reference number			
<b>1.11.31.10 Root.Transition.GoodsShipment.AdditionalInformation</b>	0		0 - 99
Additional information			
<b>1.11.31.10.1 Root.Transition.GoodsShipment.AdditionalInformation.SequenceNumber</b>	0	n....2	0 - 1
Sequence number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			

Identifier	Required/Optional	Format	Iteration
<b>1.11.31.10.2 Root.Transition.GoodsShipment.AdditionalInformation.Code</b>	0	5	0 - 1
Code ATLAS code list: IO901 Code of additional information			
<b>1.11.31.10.3 Root.Transition.GoodsShipment.AdditionalInformation.Text</b>	0	..512	0 - 1
Text Text for description of additional information			
<b>1.11.31.11 Root.Transition.GoodsShipment.Consignment</b>	0		0 - 1
Consignment			
<b>1.11.31.11.1 Root.Transition.GoodsShipment.Consignment.ContainerIndicator</b>	0	..	0 - 1
Container indicator ATLAS code list: S0027 Indication of the transport of the goods in containers.			
<b>1.11.31.11.2 Root.Transition.GoodsShipment.Consignment.InlandModeOfTransport</b>	0	..	0 - 1
Inland mode of transport ATLAS code list: C0018 Indication of the inland mode of transport.			
<b>1.11.31.11.3 Root.Transition.GoodsShipment.Consignment.ModeOfTransportAtTheBorder</b>	0	..	0 - 1
Mode of transport at the border ATLAS code list: C0018 Indication of the mode of transport at the border of the european customs area.			
<b>1.11.31.11.4 Root.Transition.GoodsShipment.Consignment.GrossMass</b>	0	n....16,3	0 - 1
Gross mass Gross mass of the consignment in kilogram			
<b>1.11.31.11.5 Root.Transition.GoodsShipment.Consignment.ReferenceNumberUCR</b>	0	..35	0 - 1
Reference number/UCR Indication of an unique consignment reference.			
<b>1.11.31.11.6 Root.Transition.GoodsShipment.Consignment.RegistrationNumberExternal</b>	0	..70	0 - 1
Registration number (external) Registration number at the border of an e.g. airwaybill			
<b>1.11.31.11.7 Root.Transition.GoodsShipment.Consignment.Carrier</b>	0		0 - 1
Carrier The carrier is, in principle, the person who brings the goods across the frontier of the customs territory of the Union or who is responsible for the movement of the goods across the frontier of the customs territory of the Union			
<b>1.11.31.11.7.1 Root.Transition.GoodsShipment.Consignment.Carrier.Code</b>	0	..250	0 - 1
Code The reference code for the business partner master data in AC.			
<b>1.11.31.11.7.2 Root.Transition.GoodsShipment.Consignment.Carrier.IdentificationNumber</b>	0	..17	0 - 1
Identification number Indication of the EORI number of the carrier			
<b>1.11.31.11.7.3 Root.Transition.GoodsShipment.Consignment.Carrier.SubsidiaryNumber</b>	0	..	0 - 1
Subsidiary number Number of the subsidiary of the carrier (stated by the German customs office)			
<b>1.11.31.11.8 Root.Transition.GoodsShipment.Consignment.Consignor</b>	0		0 - 1
Consignor			
<b>1.11.31.11.8.1 Root.Transition.GoodsShipment.Consignment.Consignor.Code</b>	0	..250	0 - 1
Code The reference code for the business partner master data in AC.			

Identifier	Required/Optional	Format	Iteration
<b>1.11.31.11.8.2 Root.Transition.GoodsShipment.Consignment.Consignor.IdentificationNumber</b>	0	..17	0 - 1
Identification number			
Indication of the EORI number of the consignor			
<b>1.11.31.11.8.3 Root.Transition.GoodsShipment.Consignment.Consignor.SubsidiaryNumber</b>	0	..	0 - 1
Subsidiary number			
Number of the subsidiary of the consignor (stated by the german customs office)			
<b>1.11.31.11.8.4 Root.Transition.GoodsShipment.Consignment.Consignor.Name</b>	0	..70	0 - 1
Name			
Name or company name of the consignor			
<b>1.11.31.11.8.5 Root.Transition.GoodsShipment.Consignment.Consignor.Address</b>	0		0 - 1
Address data of consignor			
<b>1.11.31.11.8.5.1 Root.Transition.GoodsShipment.Consignment.Consignor.Address.StreetAndNumber</b>	0	..70	0 - 1
Street and number			
<b>1.11.31.11.8.5.2 Root.Transition.GoodsShipment.Consignment.Consignor.Address.Postcode</b>	0	..17	0 - 1
Postcode			
<b>1.11.31.11.8.5.3 Root.Transition.GoodsShipment.Consignment.Consignor.Address.City</b>	0	..35	0 - 1
City			
<b>1.11.31.11.8.5.4 Root.Transition.GoodsShipment.Consignment.Consignor.Address.Country</b>	0	2	0 - 1
Country			
ATLAS code list: C0248			
Country code of the address of consignor			
<b>1.11.31.11.9 Root.Transition.GoodsShipment.Consignment.Consignee</b>	0		0 - 1
Consignee			
<b>1.11.31.11.9.1 Root.Transition.GoodsShipment.Consignment.Consignee.Code</b>	0	..250	0 - 1
Code			
The reference code for the business partner master data in AC.			
<b>1.11.31.11.9.2 Root.Transition.GoodsShipment.Consignment.Consignee.IdentificationNumber</b>	0	..17	0 - 1
Identification number			
Indication of the EORI number of the consignee			
<b>1.11.31.11.9.3 Root.Transition.GoodsShipment.Consignment.Consignee.SubsidiaryNumber</b>	0	..	0 - 1
Subsidiary number			
Number of the subsidiary of the consignee (stated by the German customs office)			
<b>1.11.31.11.9.4 Root.Transition.GoodsShipment.Consignment.Consignee.Name</b>	0	..70	0 - 1
Name			
Name or company name of the consignee			
<b>1.11.31.11.9.5 Root.Transition.GoodsShipment.Consignment.Consignee.Address</b>	0		0 - 1
Address data of consignee			
<b>1.11.31.11.9.5.1 Root.Transition.GoodsShipment.Consignment.Consignee.Address.StreetAndNumber</b>	0	..70	0 - 1
Street and number			
<b>1.11.31.11.9.5.2 Root.Transition.GoodsShipment.Consignment.Consignee.Address.Postcode</b>	0	..17	0 - 1
Postcode			
<b>1.11.31.11.9.5.3 Root.Transition.GoodsShipment.Consignment.Consignee.Address.City</b>	0	..35	0 - 1
City			
<b>1.11.31.11.9.5.4 Root.Transition.GoodsShipment.Consignment.Consignee.Address.Country</b>	0	2	0 - 1
Country			
ATLAS code list: C0248			
Country code of the address of the consignee			
<b>1.11.31.11.10 Root.Transition.GoodsShipment.Consignment.TransportEquipment</b>	0		0 - 9999
Transport equipment			

Identifier	Required/Optional	Format	Iteration
<b>1.11.31.11.10.1 Root.Transition.GoodsShipment.Consignment.TransportEquipment.SequenceNumber</b>	0	n....4	0 - 1
Sequence number  The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps			
<b>1.11.31.11.10.2 Root.Transition.GoodsShipment.Consignment.TransportEquipment.ContainerIdentificationNumber</b>	0	..17	0 - 1
Container identification number  Indication of the container number, if data field 'Idicator of conatiner' has been choosen.			
<b>1.11.31.11.10.3 Root.Transition.GoodsShipment.Consignment.TransportEquipment.GoodsReference</b>	0		0 - 999
Goods reference  Note: Indication of this data field if the data field 'Container number' is not indicated			
<b>1.11.31.11.10.3.1 Root.Transition.GoodsShipment.Consignment.TransportEquipment.GoodsReference.SequenceNumber</b>	0	n....3	0 - 1
Sequence number  The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps			
<b>1.11.31.11.10.3.2 Root.Transition.GoodsShipment.Consignment.TransportEquipment.GoodsReference.DeclarationGoodsItemNumber</b>	0	n....3	0 - 1
Declaration goods item number  Reference to the goods item number			
<b>1.11.31.11.11 Root.Transition.GoodsShipment.Consignment.LocationOfGoods</b>	0		0 - 1
Location of goods  Place of Loading of the goods and where potential seals are applied.			
<b>1.11.31.11.11.1 Root.Transition.GoodsShipment.Consignment.LocationOfGoods.TypeOfLocation</b>	0	1	0 - 1
Type of location  ATLAS code list: S0347  Type of location			
<b>1.11.31.11.11.2 Root.Transition.GoodsShipment.Consignment.LocationOfGoods.QualifierOfIdentification</b>	0	1	0 - 1
Qualifier of identification  ATLAS code list: S0326  Qualifier of identification			
<b>1.11.31.11.11.3 Root.Transition.GoodsShipment.Consignment.LocationOfGoods.AuthorisationNumber</b>	0	..35	0 - 1
Authorisation number			
<b>1.11.31.11.11.4 Root.Transition.GoodsShipment.Consignment.LocationOfGoods.AdditionalIdentifier</b>	0	4	0 - 1
Additional identifier  Location of inserting and packing within an authorisation			
<b>1.11.31.11.11.5 Root.Transition.GoodsShipment.Consignment.LocationOfGoods.UNLocode</b>	0	..17	0 - 1
UN/LOCODE  ATLAS code list: C0244  Coding of the united nations for locations for trade and transport			
<b>1.11.31.11.11.6 Root.Transition.GoodsShipment.Consignment.LocationOfGoods.GNSSLatitude</b>	0	..17	0 - 1
GNSS Latitude  Subdivisions of the degree system must be given as decimal degrees, i.e. decimal places, not in minutes and seconds.  Digit 01 - 01: Sign (an1) '+' or '-'.  Digit 02 - 03: Degree (if necessary also with leading zero) (n2)  Digit 04 - 04: Decimal separator (an1) '.'.  Digit 05 - 11: Decimal degrees (n7)  Note: Define only if the value 'W' is specified in Qualifier of identification.			



Identifier	Required/Optional	Format	Iteration
<b>1.11.31.11.11.7 Root.Transition.GoodsShipment.Consignment.LocationOfGoods.GNSSLongitude</b>	0	..17	0 - 1
GNSS Longitude  Subdivisions of the degree system must be given as decimal degrees, i.e. decimal places, not in minutes and seconds.  Digit 01 - 01: Sign (an1) '+' or '-'.  Digit 02 - 03: Degree (if necessary also with leading zero) (n2)  Digit 04 - 04: Decimal separator (an1) '.'.  Digit 05 - 11: Decimal degrees (n7)  Note: Define only if the value 'W' is specified in Qualifier of identification.			
<b>1.11.31.11.11.8 Root.Transition.GoodsShipment.Consignment.LocationOfGoods.Address</b>	0		0 - 1
Address data			
<b>1.11.31.11.11.8.1 Root.Transition.GoodsShipment.Consignment.LocationOfGoods.Address.ComplementOfInformation</b>	0	..35	0 - 1
Complement of information			
<b>1.11.31.11.11.8.2 Root.Transition.GoodsShipment.Consignment.LocationOfGoods.Address.StreetAndNumber</b>	0	..70	0 - 1
Street and number			
<b>1.11.31.11.11.8.3 Root.Transition.GoodsShipment.Consignment.LocationOfGoods.Address.Postcode</b>	0	..17	0 - 1
Postcode			
<b>1.11.31.11.11.8.4 Root.Transition.GoodsShipment.Consignment.LocationOfGoods.Address.City</b>	0	..35	0 - 1
City			
<b>1.11.31.11.11.8.5 Root.Transition.GoodsShipment.Consignment.LocationOfGoods.Address.Country</b>	0	2	0 - 1
Country  ATLAS code list: C0010  Country code of the location of goods			
<b>1.11.31.11.11.9 Root.Transition.GoodsShipment.Consignment.LocationOfGoods.ContactPerson</b>	0		0 - 1
Contact person			
<b>1.11.31.11.11.9.1 Root.Transition.GoodsShipment.Consignment.LocationOfGoods.ContactPerson.Name</b>	0	..70	0 - 1
Name of the contact person			
<b>1.11.31.11.11.9.2 Root.Transition.GoodsShipment.Consignment.LocationOfGoods.ContactPerson.PhoneNumber</b>	0	..35	0 - 1
Area code and telephone number (phone extension) of the contact person			
<b>1.11.31.11.11.9.3 Root.Transition.GoodsShipment.Consignment.LocationOfGoods.ContactPerson.EMailAddress</b>	0	..256	0 - 1
E-mail address of the contact person			
<b>1.11.31.11.12 Root.Transition.GoodsShipment.Consignment.DepartureTransportMeans</b>	0		0 - 999
Departure transport means  Means of transport at departure			
<b>1.11.31.11.12.1 Root.Transition.GoodsShipment.Consignment.DepartureTransportMeans.SequenceNumber</b>	0	n....3	0 - 1
Sequence number  The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps			
<b>1.11.31.11.12.2 Root.Transition.GoodsShipment.Consignment.DepartureTransportMeans.TypeOfIdentification</b>	0	..	0 - 1
Type of identification  ATLAS code list: C0750  Type of identification of the transport means at departure			
<b>1.11.31.11.12.3 Root.Transition.GoodsShipment.Consignment.DepartureTransportMeans.IdentificationNumber</b>	0	..35	0 - 1
Identification number  Identify of vehicle  License plate of vehicle			
<b>1.11.31.11.12.4 Root.Transition.GoodsShipment.Consignment.DepartureTransportMeans.Nationality</b>	0	2	0 - 1
Nationality  ATLAS code list: C0165  Nationality of the means of transport			

Identifier	Required/Optional	Format	Iteration
<b>1.11.31.11.13 Root.Transition.GoodsShipment.Consignment.CountryOfRoutingOfConsignment</b>	0		0 - 99
Country of Routing of Consignment  Routing of consignment  Identifiers of the countries through which the goods pass in chronological order between the country of departure and the country of destination. Especially countries in which transshipments occur.			
<b>1.11.31.11.13.1 Root.Transition.GoodsShipment.Consignment.CountryOfRoutingOfConsignment.SequenceNumber</b>	0	n....2	0 - 1
Sequence number  The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps			
<b>1.11.31.11.13.2 Root.Transition.GoodsShipment.Consignment.CountryOfRoutingOfConsignment.Country</b>	0	2	0 - 1
Country  ATLAS code list: C0008  Country code			
<b>1.11.31.11.14 Root.Transition.GoodsShipment.Consignment.ActiveBorderTransportMeans</b>	0		0 - 1
Active border transport means  Active means of transport (border).  Indication if data field 'mode of transport at the border' is indicated.			
<b>1.11.31.11.14.1 Root.Transition.GoodsShipment.Consignment.ActiveBorderTransportMeans.TypeOfIdentification</b>	0	..	0 - 1
Type of identification  ATLAS code list: C0219  Type of identification of the transport means			
<b>1.11.31.11.14.2 Root.Transition.GoodsShipment.Consignment.ActiveBorderTransportMeans.IdentificationNumber</b>	0	..35	0 - 1
Identification number  Identify of vehicle			
<b>1.11.31.11.14.3 Root.Transition.GoodsShipment.Consignment.ActiveBorderTransportMeans.Nationality</b>	0	2	0 - 1
Nationality  ATLAS code list: C0165  Nationality of the means of transport			
<b>1.11.31.11.15 Root.Transition.GoodsShipment.Consignment.TransportDocument</b>	0		0 - 99
Transport document			
<b>1.11.31.11.15.1 Root.Transition.GoodsShipment.Consignment.TransportDocument.SequenceNumber</b>	0	n....2	0 - 1
Sequence number  The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
<b>1.11.31.11.15.2 Root.Transition.GoodsShipment.Consignment.TransportDocument.TypeAndQualifier</b>	0	..8	0 - 1
Type and qualifier  ATLAS code list: IO941  Type and Qualifier of transport document			
<b>1.11.31.11.15.3 Root.Transition.GoodsShipment.Consignment.TransportDocument.ReferenceNumber</b>	0	..70	0 - 1
Reference number  Reference number of transport document			
<b>1.11.31.11.16 Root.Transition.GoodsShipment.Consignment.PaymentMethodTransport</b>	0	1	0 - 1
Payment method transport  ATLAS code list: C0116  Method of payment of the transport charges			
<b>1.11.31.12 Root.Transition.GoodsShipment.GoodsItem</b>	0		0 - 999
Goods item			
<b>1.11.31.12.1 Root.Transition.GoodsShipment.GoodsItem.SequenceNumber</b>	0	n....3	0 - 1
Sequence number  The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			

Identifier	Required/Optional	Format	Iteration
<b>1.11.31.12.2 Root.Transition.GoodsShipment.GoodsItem.StatisticalValue</b>	0	n....16,2	0 - 1
Statistical value  Statistic value of the declared goods			
<b>1.11.31.12.3 Root.Transition.GoodsShipment.GoodsItem.NatureOfTransaction</b>	0	..	0 - 1
Nature of transaction  In this data field, the type of transaction (information from which certain clauses of the business contract become apparent) is to be indicated with the key number accordingly.			
<b>1.11.31.12.4 Root.Transition.GoodsShipment.GoodsItem.CountryOfExport</b>	0	2	0 - 1
Country of export  ATLAS code list: CO010  Actual country of export			
<b>1.11.31.12.5 Root.Transition.GoodsShipment.GoodsItem.ReferenceNumberUCR</b>	0	..35	0 - 1
Reference number/UCR  Indication of unique reference number			
<b>1.11.31.12.6 Root.Transition.GoodsShipment.GoodsItem.RegistrationNumberExternal</b>	0	..70	0 - 1
Registration number (external)  Registration number at the border of an e.g. airwaybill			
<b>1.11.31.12.7 Root.Transition.GoodsShipment.GoodsItem.Authorisation</b>	0		0 - 9
Authorisation			
<b>1.11.31.12.7.1 Root.Transition.GoodsShipment.GoodsItem.Authorisation.SequenceNumber</b>	0	n....1	0 - 1
Sequence number  The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
<b>1.11.31.12.7.2 Root.Transition.GoodsShipment.GoodsItem.Authorisation.Type</b>	0	4	0 - 1
Type  ATLAS code list: SO615  Type of authorisation			
<b>1.11.31.12.7.3 Root.Transition.GoodsShipment.GoodsItem.Authorisation.ReferenceNumber</b>	0	..35	0 - 1
Reference number  Authorisation number			
<b>1.11.31.12.7.4 Root.Transition.GoodsShipment.GoodsItem.Authorisation.HolderOfAuthorisation</b>	0	..17	0 - 1
Holder of authorisation			
<b>1.11.31.12.8 Root.Transition.GoodsShipment.GoodsItem.Procedure</b>	0	..8	0 - 1
Procedure  Enter the customs procedure or use for which the goods are declared.			
<b>1.11.31.12.9 Root.Transition.GoodsShipment.GoodsItem.Consignor</b>	0		0 - 1
Consignor			
<b>1.11.31.12.9.1 Root.Transition.GoodsShipment.GoodsItem.Consignor.Code</b>	0	..250	0 - 1
Code  The reference code for the business partner master data in AC.			
<b>1.11.31.12.9.2 Root.Transition.GoodsShipment.GoodsItem.Consignor.IdentificationNumber</b>	0	..17	0 - 1
Identification number  Indication of the EORI number of the consignor			
<b>1.11.31.12.9.3 Root.Transition.GoodsShipment.GoodsItem.Consignor.SubsidiaryNumber</b>	0	..	0 - 1
Subsidiary number  Number of the subsidiary of the consignor (stated by the german customs office)			
<b>1.11.31.12.9.4 Root.Transition.GoodsShipment.GoodsItem.Consignor.Name</b>	0	..70	0 - 1
Name  Name or company name of the consignor			

Identifier	Required/Optional	Format	Iteration
<b>1.11.31.12.9.5 Root.Transition.GoodsShipment.GoodsItem.Consignor.Address</b>	0		0 - 1
Address data of consignor			
<b>1.11.31.12.9.5.1 Root.Transition.GoodsShipment.GoodsItem.Consignor.Address.StreetAndNumber</b>	0	..70	0 - 1
Street and number			
<b>1.11.31.12.9.5.2 Root.Transition.GoodsShipment.GoodsItem.Consignor.Address.Postcode</b>	0	..17	0 - 1
Postcode			
<b>1.11.31.12.9.5.3 Root.Transition.GoodsShipment.GoodsItem.Consignor.Address.City</b>	0	..35	0 - 1
City			
<b>1.11.31.12.9.5.4 Root.Transition.GoodsShipment.GoodsItem.Consignor.Address.Country</b>	0	2	0 - 1
Country			
ATLAS code list: C0248			
Country code of the address of the consignor			
<b>1.11.31.12.10 Root.Transition.GoodsShipment.GoodsItem.Consignee</b>	0		0 - 1
Consignee			
<b>1.11.31.12.10.1 Root.Transition.GoodsShipment.GoodsItem.Consignee.Code</b>	0	..250	0 - 1
Code			
The reference code for the business partner master data in AC.			
<b>1.11.31.12.10.2 Root.Transition.GoodsShipment.GoodsItem.Consignee.IdentificationNumber</b>	0	..17	0 - 1
Identification number			
Indication of the EORI number of the consignee			
<b>1.11.31.12.10.3 Root.Transition.GoodsShipment.GoodsItem.Consignee.SubsidiaryNumber</b>	0	..	0 - 1
Subsidiary number			
Number of the subsidiary of the consignee (stated by the German customs office)			
<b>1.11.31.12.10.4 Root.Transition.GoodsShipment.GoodsItem.Consignee.Name</b>	0	..70	0 - 1
Name			
Name or company name of the consignee			
<b>1.11.31.12.10.5 Root.Transition.GoodsShipment.GoodsItem.Consignee.Address</b>	0		0 - 1
Address data of the consignee			
<b>1.11.31.12.10.5.1 Root.Transition.GoodsShipment.GoodsItem.Consignee.Address.StreetAndNumber</b>	0	..70	0 - 1
Street and number			
<b>1.11.31.12.10.5.2 Root.Transition.GoodsShipment.GoodsItem.Consignee.Address.Postcode</b>	0	..17	0 - 1
Postcode			
<b>1.11.31.12.10.5.3 Root.Transition.GoodsShipment.GoodsItem.Consignee.Address.City</b>	0	..35	0 - 1
City			
<b>1.11.31.12.10.5.4 Root.Transition.GoodsShipment.GoodsItem.Consignee.Address.Country</b>	0	2	0 - 1
Country			
ATLAS code list: C0248			
Country code of the address of the consignee			
<b>1.11.31.12.11 Root.Transition.GoodsShipment.GoodsItem.AdditionalSupplyChainActor</b>	0		0 - 99
Additional supply chain actor			
<b>1.11.31.12.11.1 Root.Transition.GoodsShipment.GoodsItem.AdditionalSupplyChainActor.SequenceNumber</b>	0	n....2	0 - 1
Sequence number			
The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
<b>1.11.31.12.11.2 Root.Transition.GoodsShipment.GoodsItem.AdditionalSupplyChainActor.Role</b>	0	..3	0 - 1
Role			
ATLAS code list: C0704			
Role of the additional supply chain actor			

Identifier	Required/Optional	Format	Iteration
<b>1.11.31.12.11.3 Root.Transition.GoodsShipment.GoodsItem.AdditionalSupplyChainActor.Code</b>	0	..250	0 - 1
Code  The reference code for the business partner master data in AC.			
<b>1.11.31.12.11.4 Root.Transition.GoodsShipment.GoodsItem.AdditionalSupplyChainActor.IdentificationNumber</b>	0	..17	0 - 1
Identification number  Indication of the EORI number of the additional supply chain actor			
<b>1.11.31.12.12 Root.Transition.GoodsShipment.GoodsItem.CountryOfOrigin</b>	0	2	0 - 1
Country of origin  ATLAS code list: C0248  Country code of the origin country			
<b>1.11.31.12.13 Root.Transition.GoodsShipment.GoodsItem.RegionOfDispatch</b>	0	..9	0 - 1
Region of dispatch  Code of the origin federal state of the goods			
<b>1.11.31.12.14 Root.Transition.GoodsShipment.GoodsItem.DescriptionOfGoods</b>	0	..512	0 - 1
Description of goods			
<b>1.11.31.12.15 Root.Transition.GoodsShipment.GoodsItem.CusCode</b>	0	9	0 - 1
CUS-number  ATLAS code list: C0016  CUS-number(Customs Union and Statistics)  The CUS code is an identifier given to assigned to chemical substances and preparations within the framework of the European Customs of Chemical Products (ECICS).			
<b>1.11.31.12.16 Root.Transition.GoodsShipment.GoodsItem.CommodityCode</b>	0	..	0 - 1
Commodity code			
<b>1.11.31.12.17 Root.Transition.GoodsShipment.GoodsItem.TARICAdditionalCode</b>	0		0 - 99
TARIC additional code			
<b>1.11.31.12.17.1 Root.Transition.GoodsShipment.GoodsItem.TARICAdditionalCode.SequenceNumber</b>	0	n....2	0 - 1
Sequence number  The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
<b>1.11.31.12.17.2 Root.Transition.GoodsShipment.GoodsItem.TARICAdditionalCode.TaricAdditionalCode</b>	0	..	0 - 1
TARIC additional code			
<b>1.11.31.12.18 Root.Transition.GoodsShipment.GoodsItem.DangerousGoods</b>	0		0 - 99
Dangerous goods  Details of dangerous goods			
<b>1.11.31.12.18.1 Root.Transition.GoodsShipment.GoodsItem.DangerousGoods.SequenceNumber</b>	0	n....2	0 - 1
Sequence number  The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
<b>1.11.31.12.18.2 Root.Transition.GoodsShipment.GoodsItem.DangerousGoods.UNNumber</b>	0	..	0 - 1
UN number  ATLAS code list: C0101  UN number for dangerous goods			
<b>1.11.31.12.19 Root.Transition.GoodsShipment.GoodsItem.GrossMass</b>	0	n....16,3	0 - 1
Gross mass  Gross mass in kilogram			
<b>1.11.31.12.20 Root.Transition.GoodsShipment.GoodsItem.NetMass</b>	0	n....16,6	0 - 1
Net mass  Net mass in kilogram			
<b>1.11.31.12.21 Root.Transition.GoodsShipment.GoodsItem.SupplementaryUnits</b>	0	n....16,6	0 - 1
Supplementary units  Supplementary unites depends on the commodity code.			

Identifier	Required/ Optional	Format	Iteration
<b>1.11.31.12.22 Root.Transition.GoodsShipment.GoodsItem.Packaging</b>	0		0 - 99
Packaging			
<b>1.11.31.12.22.1 Root.Transition.GoodsShipment.GoodsItem.Packaging.SequenceNumber</b>	0	n....2	0 - 1
Sequence number			
The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
<b>1.11.31.12.22.2 Root.Transition.GoodsShipment.GoodsItem.Packaging.TypeOfPackages</b>	0	2	0 - 1
Type of packages			
ATLAS code list: C0017			
Type of packages			
<b>1.11.31.12.22.3 Root.Transition.GoodsShipment.GoodsItem.Packaging.NumberOfPackages</b>	0	n....8	0 - 1
Number of packages			
Number of pieces packed in the same type and with the same shipping mark or, in the case of unpacked goods, the number of items covered.			
<b>1.11.31.12.22.4 Root.Transition.GoodsShipment.GoodsItem.Packaging.ShippingMarks</b>	0	..512	0 - 1
Shipping marks			
The mark or number with which a package is marked.			
<b>1.11.31.12.22.5 Root.Transition.GoodsShipment.GoodsItem.Packaging.PackageReference</b>	0	n....3	0 - 1
Package reference			
Reference to packages of another item of goods which have been packed together			
<b>1.11.31.12.23 Root.Transition.GoodsShipment.GoodsItem.PreviousDocument</b>	0		0 - 99
Previous document			
<b>1.11.31.12.23.1 Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.SequenceNumber</b>	0	n....2	0 - 1
Sequence number			
The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
<b>1.11.31.12.23.2 Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.TypeAndQualifier</b>	0	..8	0 - 1
Type and Qualifier			
ATLAS code list: IO932			
Type and qualifier of previous document			
<b>1.11.31.12.23.3 Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.ReferenceNumber</b>	0	..70	0 - 1
Reference number			
Reference number of previous document			
<b>1.11.31.12.23.4 Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.GoodsItemNumber</b>	0	n....5	0 - 1
Goods item number			
<b>1.11.31.12.23.5 Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.MeasurementUnitAndQualifier</b>	0	..4	0 - 1
Measurement unit and qualifier			
ATLAS code list: C0349			
Unit of measurement for the quantity of goods to be transferred from the previous procedure.			
<b>1.11.31.12.23.6 Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.Quantity</b>	0	n....16,6	0 - 1
Quantity			
Quantity of goods to be transferred from the previous procedure.			
<b>1.11.31.12.23.7 Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.ComplementOfInformation</b>	0	..35	0 - 1
Complement of information			
Additional textual description of the previous document.			
<b>1.11.31.12.24 Root.Transition.GoodsShipment.GoodsItem.SupportingDocument</b>	0		0 - 99
Supporting document			
<b>1.11.31.12.24.1 Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.SequenceNumber</b>	0	n....2	0 - 1
Sequence number			
The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			

Identifier	Required/Optional	Format	Iteration
<b>1.11.31.12.24.2 Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.TypeAndQualifier</b>	0	..8	0 - 1
Type and qualifier ATLAS code list: IO922 Type and qualifier of supporting document			
<b>1.11.31.12.24.3 Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.ReferenceNumber</b>	0	..70	0 - 1
Reference number Reference number of the supporting document			
<b>1.11.31.12.24.4 Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.DocumentLineNumber</b>	0	n....5	0 - 1
Document line item number Reference to a numbered entry in the document.			
<b>1.11.31.12.24.5 Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.ComplementOfInformation</b>	0	..35	0 - 1
Complement of information Additional textual description of the supporting document.			
<b>1.11.31.12.24.6 Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.Detail</b>	0	..12	0 - 1
Detail Details of a document that can be presented.			
<b>1.11.31.12.24.7 Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.IssuingAuthorityName</b>	0	..70	0 - 1
Issuing authority name Authority that issued the document			
<b>1.11.31.12.24.8 Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.IssuingDate</b>	0	..	0 - 1
Issuing date Date on which the document was issued			
<b>1.11.31.12.24.9 Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.ValidityDate</b>	0	..	0 - 1
Validity date Date of the last validity of the document			
<b>1.11.31.12.24.10 Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.MeasurementUnitAndQualifier</b>	0	..4	0 - 1
Measurement unit and qualifier ATLAS code list: C0349 EU unit of measurement for the quantity of goods.			
<b>1.11.31.12.24.11 Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.ComplementaryUnit</b>	0	..10	0 - 1
Complementary unit ATLAS code list: A0140 BAFA unit of measurement for the quantity of goods and, if applicable, the quantity of depreciation.			
<b>1.11.31.12.24.12 Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.Quantity</b>	0	n....16,6	0 - 1
Quantity Quantity of goods of that part of the item of goods which is authorised by the specified document.			
<b>1.11.31.12.24.13 Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.Currency</b>	0	3	0 - 1
Currency ATLAS code list: C0352 Currency of export value			
<b>1.11.31.12.24.14 Root.Transition.GoodsShipment.GoodsItem.SupportingDocument.Amount</b>	0	n....16,2	0 - 1
Amount Export value of that portion of the item of goods authorised by the specified document. Value of goods to be written off on the export licence or certificate.			
<b>1.11.31.12.25 Root.Transition.GoodsShipment.GoodsItem.AdditionalReference</b>	0		0 - 99
Additional reference			



Identifier	Required/Optional	Format	Iteration
<b>1.11.31.12.25.1 Root.Transition.GoodsShipment.GoodsItem.AdditionalReference.SequenceNumber</b>	0	n....2	0 - 1
Sequence number  The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
<b>1.11.31.12.25.2 Root.Transition.GoodsShipment.GoodsItem.AdditionalReference.TypeAndQualifier</b>	0	..8	0 - 1
Type and qualifier  ATLAS code list: IO912  Type and qualifier of additional reference			
<b>1.11.31.12.25.3 Root.Transition.GoodsShipment.GoodsItem.AdditionalReference.ReferenceNumber</b>	0	..70	0 - 1
Reference number  Reference number of the additional reference			
<b>1.11.31.12.25.4 Root.Transition.GoodsShipment.GoodsItem.AdditionalReference.Detail</b>	0	..12	0 - 1
Detail  Details of the reference			
<b>1.11.31.12.25.5 Root.Transition.GoodsShipment.GoodsItem.AdditionalReference.Currency</b>	0	3	0 - 1
Currency  ATLAS code list: C0352  Currency of export value			
<b>1.11.31.12.25.6 Root.Transition.GoodsShipment.GoodsItem.AdditionalReference.Amount</b>	0	n....16,2	0 - 1
Amount  Value of goods subject to the provisions of the reference.			
<b>1.11.31.12.26 Root.Transition.GoodsShipment.GoodsItem.AdditionalInformation</b>	0		0 - 99
Additional information			
<b>1.11.31.12.26.1 Root.Transition.GoodsShipment.GoodsItem.AdditionalInformation.SequenceNumber</b>	0	n....2	0 - 1
Sequence number  The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
<b>1.11.31.12.26.2 Root.Transition.GoodsShipment.GoodsItem.AdditionalInformation.Code</b>	0	5	0 - 1
Code  The reference code for the business partner master data in AC.			
<b>1.11.31.12.26.3 Root.Transition.GoodsShipment.GoodsItem.AdditionalInformation.Text</b>	0	..512	0 - 1
Text  Text for description of additional information			
<b>1.11.31.12.27 Root.Transition.GoodsShipment.GoodsItem.PaymentMethodTransport</b>	0	1	0 - 1
Payment method transport  ATLAS code list: C0116  Method of payment (Transport charges)			
<b>1.11.31.12.28 Root.Transition.GoodsShipment.GoodsItem.OutwardProcessing</b>	0		0 - 1
Outward processing  Information on the transfer under the customs outward processing procedure.			
<b>1.11.31.12.28.1 Root.Transition.GoodsShipment.GoodsItem.OutwardProcessing.Replacement</b>	0	..	0 - 1
Replacement  ATLAS code list: S0027  Indicator whether a standard exchange or an exchange of equivalent goods under the outward processing procedure is requested.			
<b>1.11.31.12.28.2 Root.Transition.GoodsShipment.GoodsItem.OutwardProcessing.ReimportDate</b>	0	..	0 - 1
Reimport date  Last possible day for reimportation of compensating products			
<b>1.11.31.12.29 Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing</b>	0		0 - 1
Customs warehousing  Termination information from a customs warehousing procedure.			

Identifier	Required/ Optional	Format	Iteration
<b>1.11.31.12.29.1 Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.LRN</b>	0	..35	0 - 1
LRN Internal classification criterion assigned as a reference number by the warehouse keeper participating in the ATLAS procedure.			
<b>1.11.31.12.29.2 Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.Authorisation</b>	0		0 - 1
Authorisation Authorisation granted by the customs authorities			
<b>1.11.31.12.29.2.1 Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.Authorisation.Type</b>	0	4	0 - 1
Type ATLAS code list: A1258 Type of authorisation			
<b>1.11.31.12.29.2.2 Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.Authorisation.ReferenceNumber</b>	0	..35	0 - 1
Reference number The authorisation reference number must be indicated.			
<b>1.11.31.12.29.3 Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference</b>	0		0 - 999
Goods reference Item to be deducted in the bonded warehouse			
<b>1.11.31.12.29.3.1 Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.SequenceNumber</b>	0	n....3	0 - 1
Sequence number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
<b>1.11.31.12.29.3.2 Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.AccessViaATLAS</b>	0	..	0 - 1
Access via ATLAS ATLAS code list: S0027 Indicator whether the consignment was declared via ATLAS			
<b>1.11.31.12.29.3.3 Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.MRN</b>	0	18	0 - 1
MRN Specification of the assigned Master Reference Number (MRN). Note: The indication of the data field is required and only allowed if the data field 'Customs warehousing - Goods reference - registration number' is not indicated.			
<b>1.11.31.12.29.3.4 Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.RegistrationNumber</b>	0	..35	0 - 1
Registration number Registration number of warehouse stock Note: The indication of the data field is required and only allowed if the data field 'Customs warehousing - Goods reference - MRN' is not indicated.			
<b>1.11.31.12.29.3.5 Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.GoodsItemNumber</b>	0	n....5	0 - 1
Goods item Goods item number of warehouse stock			
<b>1.11.31.12.29.3.6 Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.UsualTreatment</b>	0	..	0 - 1
Usual treatment ATLAS code list: S0027 Indicates whether the goods have been subjected to usual treatment.			
<b>1.11.31.12.29.3.7 Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.ComplementOfInformation</b>	0	..100	0 - 1
Complement of information			
<b>1.11.31.12.29.3.8 Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.CommodityCode</b>	0	..	0 - 1
Commodity code			
<b>1.11.31.12.29.3.9 Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.GoodsReduction</b>	0		0 - 1
Goods reduction (customs warehousing)			

Identifier	Required/Optional	Format	Iteration
<b>1.11.31.12.29.3.9.1 Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.GoodsReduction.MeasurementUnitAndQualifier</b>	0	..5	0 - 1
Measurement unit and qualifier			
ATLAS code list: IO700			
Measurement unit and qualifier of goods reduction			
<b>1.11.31.12.29.3.9.2 Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.GoodsReduction.Quantity</b>	0	n....12,3	0 - 1
Quantity			
<b>1.11.31.12.29.3.10 Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.GoodsReductionAfterTreatment</b>	0		0 - 1
Goods reduction after treatment			
Indication of quantity after treatment			
Note: In this data group a quantity may be indicated if the unit of measurement and/or quantity after customary treatment differ from those in the data group 'departure quantity'.			
<b>1.11.31.12.29.3.10.1 Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.GoodsReductionAfterTreatment.MeasurementUnitAndQualifier</b>	0	..5	0 - 1
Measurement unit and qualifier			
ATLAS code list: IO700			
Measurement unit and qualifier of goods reduction after treatment			
<b>1.11.31.12.29.3.10.2 Root.Transition.GoodsShipment.GoodsItem.CustomsWarehousing.GoodsReference.GoodsReductionAfterTreatment.Quantity</b>	0	n....12,3	0 - 1
Quantity			
<b>1.11.31.12.30 Root.Transition.GoodsShipment.GoodsItem.InwardProcessing</b>	0		0 - 1
Inward processing			
Discharge of the customs procedure inward processing.			
Note: The specification of the data group is required and only permissible if a data field 'process / previous process' s registered with value '51'.			
<b>1.11.31.12.30.1 Root.Transition.GoodsShipment.GoodsItem.InwardProcessing.SimplyGrantedAuthorisation</b>	0	..	0 - 1
Simply granted authorisation			
ATLAS code list: S0027			
Indicator whether the authorisation was applied for and granted on the basis of a customs declaration.			
<b>1.11.31.12.30.2 Root.Transition.GoodsShipment.GoodsItem.InwardProcessing.Authorisation</b>	0		0 - 1
Authorisation			
Note: The entry is required and only permitted if the data field 'Inward processing - Simplified authorisation granted' is entered with the value '0'.			
<b>1.11.31.12.30.2.1 Root.Transition.GoodsShipment.GoodsItem.InwardProcessing.Authorisation.Type</b>	0	4	0 - 1
Type			
ATLAS code list: A1259			
Type of authorisation			
<b>1.11.31.12.30.2.2 Root.Transition.GoodsShipment.GoodsItem.InwardProcessing.Authorisation.ReferenceNumber</b>	0	..35	0 - 1
Reference number			
The authorisation reference number must be indicated.			
<b>1.11.31.12.30.3 Root.Transition.GoodsShipment.GoodsItem.InwardProcessing.CustomsOfficeOfSupervision</b>	0	8	0 - 1
Customs office of supervision			
Customs office of supervision of the inward processing			
<b>1.11.31.12.30.4 Root.Transition.GoodsShipment.GoodsItem.InwardProcessing.GoodsReference</b>	0		0 - 999
Goods reference			
Item to be deducted of the inward processing			
<b>1.11.31.12.30.4.1 Root.Transition.GoodsShipment.GoodsItem.InwardProcessing.GoodsReference.SequenceNumber</b>	0	n....3	0 - 1
Sequence number			
The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			

Identifier	Required/Optional	Format	Iteration
<b>1.11.31.12.30.4.2 Root.Transition.GoodsShipment.GoodsItem.InwardProcessing.GoodsReference.AccessViaATLAS</b>	0	..	0 - 1
Access via ATLAS ATLAS code list: SOO27 Indicator whether the consignment was declared via ATLAS.			
<b>1.11.31.12.30.4.3 Root.Transition.GoodsShipment.GoodsItem.InwardProcessing.GoodsReference.MRN</b>	0	18	0 - 1
MRN Indication of the master reference number (MRN) Note: The indication of the data field is required and only allowed if the data field 'Inward processing - Goods reference - registration number' is not indicated.			
<b>1.11.31.12.30.4.4 Root.Transition.GoodsShipment.GoodsItem.InwardProcessing.GoodsReference.RegistrationNumber</b>	0	..35	0 - 1
Registration number Registration number of inward processing, Note: The indication of the data field is required and only allowed if the data field 'Inward processing - Goods reference - MRN' is not indicated.			
<b>1.11.31.12.30.4.5 Root.Transition.GoodsShipment.GoodsItem.InwardProcessing.GoodsReference.GoodsItemNumber</b>	0	n....5	0 - 1
Goods item number Goods item number of inward processing.			
<b>1.11.31.12.30.4.6 Root.Transition.GoodsShipment.GoodsItem.InwardProcessing.GoodsReference.GoodsRelatedData</b>	0	..350	0 - 1
Goods-related data Goods related data and information			
<b>1.11.31.12.31 Root.Transition.GoodsShipment.GoodsItem.AdditionalId</b>	0	..35	0 - 1
Additional reference number A reference field at item level to indicate an internal reference. (no transmission to ATLAS)			
<b>1.11.31.12.32 Root.Transition.GoodsShipment.GoodsItem.QuantityOfGoods</b>	0	n....12,3	0 - 1
Quantity of goods The indication of the quantity of goods of a goods item. (no transmission to ATLAS)			
<b>1.11.31.12.33 Root.Transition.GoodsShipment.GoodsItem.QuantityOfGoodsMeasurement</b>	0	..5	0 - 1
Unit of measurement of the quantity of goods The indication of the unit of measurement. (no transmission to ATLAS)			
<b>1.11.31.12.34 Root.Transition.GoodsShipment.GoodsItem.ArticleNumber</b>	0	..35	0 - 1
Article number The article number is used to reference the article master data in AC. (no transmission to ATLAS)			
<b>1.11.31.12.35 Root.Transition.GoodsShipment.GoodsItem.TransportCosts</b>	0	n....15,2	0 - 1
The transport costs is used in combination with the invoice value to calculate the statistical value. The transport costs are not transferred to ATLAS.			
<b>1.11.31.12.36 Root.Transition.GoodsShipment.GoodsItem.TransportCostsCurrency</b>	0	3	0 - 1
The currency belongs to the transport costs. The information is not transmitted to ATLAS.			
<b>1.11.31.12.37 Root.Transition.GoodsShipment.GoodsItem.InvoiceAmount</b>	0	n....15,2	0 - 1
Invoice amount Invoice price of the goods item. (no transmission to ATLAS)			
<b>1.11.31.12.38 Root.Transition.GoodsShipment.GoodsItem.InvoiceCurrency</b>	0	3	0 - 1
Invoice currency The currency of the invoice amount. (no transmission to ATLAS)			