

Key: AESExport_DE_IN_XML_AI
XSD: interfaceDescription_AESExport_DE_IN_XML_AI - Ergaenzende Ausfuhranmeldung - 1.2.0.xsd
Document-Version: interfaceDescription_AESExport_DE_IN_XML_AI - Ergaenzende Ausfuhranmeldung - 1.2.0
Notes:

1	Root
1.1	Root.Client
1.2	Root.User
1.3	Root.CountryOfLodgement
1.4	Root.OperationDomain
1.5	Root.OperationType
1.6	Root.ID
1.7	Root.ReferenceNumber
1.8	Root.AdditionalReferenceNumber
1.9	Root.StatusNotificationEmail
1.10	Root.Meta
1.10.1	Root.Meta.Operation
1.10.2	Root.Meta.ReferenceType
1.10.3	Root.Meta.ShipmentNumber
1.11	Root.Transition
1.11.1	Root.Transition.TransitionType
1.11.2	Root.Transition.MRN
1.11.3	Root.Transition.SupplementSubmissionDateAndTime
1.11.4	Root.Transition.SupplementSubmissionTimezone
1.11.5	Root.Transition.TotalAmountInvoiced
1.11.6	Root.Transition.InvoiceCurrency
1.11.7	Root.Transition.CustomsOfficeOfSupplement
1.11.8	Root.Transition.Declarant
1.11.8.1	Root.Transition.Declarant.Code
1.11.8.2	Root.Transition.Declarant.IdentificationNumber
1.11.8.3	Root.Transition.Declarant.SubsidiaryNumber
1.11.9	Root.Transition.GoodsShipment
1.11.9.1	Root.Transition.GoodsShipment.NatureOfTransaction
1.11.9.2	Root.Transition.GoodsShipment.DeliveryTerms
1.11.9.2.1	Root.Transition.GoodsShipment.DeliveryTerms.IncotermsCode
1.11.9.2.2	Root.Transition.GoodsShipment.DeliveryTerms.UNLocode
1.11.9.2.3	Root.Transition.GoodsShipment.DeliveryTerms.Location
1.11.9.2.4	Root.Transition.GoodsShipment.DeliveryTerms.Country
1.11.9.2.5	Root.Transition.GoodsShipment.DeliveryTerms.Text
1.11.9.3	Root.Transition.GoodsShipment.PreviousDocument
1.11.9.3.1	Root.Transition.GoodsShipment.PreviousDocument.SequenceNumber
1.11.9.3.2	Root.Transition.GoodsShipment.PreviousDocument.TypeAndQualifier
1.11.9.3.3	Root.Transition.GoodsShipment.PreviousDocument.ReferenceNumber
1.11.9.4	Root.Transition.GoodsShipment.Consignment
1.11.9.4.1	Root.Transition.GoodsShipment.Consignment.ContainerIndicator
1.11.9.4.2	Root.Transition.GoodsShipment.Consignment.InlandModeOfTransport
1.11.9.4.3	Root.Transition.GoodsShipment.Consignment.ModeOfTransportAtTheBorder
1.11.9.4.4	Root.Transition.GoodsShipment.Consignment.Consignee
1.11.9.4.4.1	Root.Transition.GoodsShipment.Consignment.Consignee.Code
1.11.9.4.4.2	Root.Transition.GoodsShipment.Consignment.Consignee.IdentificationNumber
1.11.9.4.4.3	Root.Transition.GoodsShipment.Consignment.Consignee.SubsidiaryNumber
1.11.9.4.4.4	Root.Transition.GoodsShipment.Consignment.Consignee.Name
1.11.9.4.4.5	Root.Transition.GoodsShipment.Consignment.Consignee.Address
1.11.9.4.4.5.1	Root.Transition.GoodsShipment.Consignment.Consignee.Address.StreetAndNumber
1.11.9.4.4.5.2	Root.Transition.GoodsShipment.Consignment.Consignee.Address.Postcode
1.11.9.4.4.5.3	Root.Transition.GoodsShipment.Consignment.Consignee.Address.City
1.11.9.4.4.5.4	Root.Transition.GoodsShipment.Consignment.Consignee.Address.Country
1.11.9.4.5	Root.Transition.GoodsShipment.Consignment.TransportEquipment
1.11.9.4.5.1	Root.Transition.GoodsShipment.Consignment.TransportEquipment.SequenceNumber
1.11.9.4.5.2	Root.Transition.GoodsShipment.Consignment.TransportEquipment.ContainerIdentificationNumber
1.11.9.4.5.3	Root.Transition.GoodsShipment.Consignment.TransportEquipment.GoodsReference
1.11.9.4.5.3.1	Root.Transition.GoodsShipment.Consignment.TransportEquipment.GoodsReference.SequenceNumber
1.11.9.4.5.3.2	Root.Transition.GoodsShipment.Consignment.TransportEquipment.GoodsReference.DeclarationGoodsItemNumber
1.11.9.4.6	Root.Transition.GoodsShipment.Consignment.DepartureTransportMeans
1.11.9.4.6.1	Root.Transition.GoodsShipment.Consignment.DepartureTransportMeans.SequenceNumber
1.11.9.4.6.2	Root.Transition.GoodsShipment.Consignment.DepartureTransportMeans.TypeOfIdentification

1.11.9.4.6.3	Root.Transition.GoodsShipment.Consignment.DepartureTransportMeans.IdentificationNumber
1.11.9.4.6.4	Root.Transition.GoodsShipment.Consignment.DepartureTransportMeans.Nationality
1.11.9.4.7	Root.Transition.GoodsShipment.Consignment.ActiveBorderTransportMeans
1.11.9.4.7.1	Root.Transition.GoodsShipment.Consignment.ActiveBorderTransportMeans.TypeOfIdentification
1.11.9.4.7.2	Root.Transition.GoodsShipment.Consignment.ActiveBorderTransportMeans.IdentificationNumber
1.11.9.4.7.3	Root.Transition.GoodsShipment.Consignment.ActiveBorderTransportMeans.Nationality
1.11.9.5	Root.Transition.GoodsShipment.GoodsItem
1.11.9.5.1	Root.Transition.GoodsShipment.GoodsItem.SequenceNumber
1.11.9.5.2	Root.Transition.GoodsShipment.GoodsItem.StatisticalValue
1.11.9.5.3	Root.Transition.GoodsShipment.GoodsItem.NatureOfTransaction
1.11.9.5.4	Root.Transition.GoodsShipment.GoodsItem.Consignee
1.11.9.5.4.1	Root.Transition.GoodsShipment.GoodsItem.Consignee.Code
1.11.9.5.4.2	Root.Transition.GoodsShipment.GoodsItem.Consignee.IdentificationNumber
1.11.9.5.4.3	Root.Transition.GoodsShipment.GoodsItem.Consignee.SubsidiaryNumber
1.11.9.5.4.4	Root.Transition.GoodsShipment.GoodsItem.Consignee.Name
1.11.9.5.4.5	Root.Transition.GoodsShipment.GoodsItem.Consignee.Address
1.11.9.5.4.5.1	Root.Transition.GoodsShipment.GoodsItem.Consignee.Address.StreetAndNumber
1.11.9.5.4.5.2	Root.Transition.GoodsShipment.GoodsItem.Consignee.Address.Postcode
1.11.9.5.4.5.3	Root.Transition.GoodsShipment.GoodsItem.Consignee.Address.City
1.11.9.5.4.5.4	Root.Transition.GoodsShipment.GoodsItem.Consignee.Address.Country
1.11.9.5.5	Root.Transition.GoodsShipment.GoodsItem.CountryOfOrigin
1.11.9.5.6	Root.Transition.GoodsShipment.GoodsItem.RegionOfDispatch
1.11.9.5.7	Root.Transition.GoodsShipment.GoodsItem.SupplementaryUnits
1.11.9.5.8	Root.Transition.GoodsShipment.GoodsItem.PreviousDocument
1.11.9.5.8.1	Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.SequenceNumber
1.11.9.5.8.2	Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.TypeAndQualifier
1.11.9.5.8.3	Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.ReferenceNumber
1.11.9.5.8.4	Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.GoodsItemNumber
1.11.9.5.8.5	Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.MeasurementUnitAndQualifier
1.11.9.5.8.6	Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.Quantity
1.11.9.5.8.7	Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.ComplementOfInformation

Identifier		Required/ Optional	Format	Iteration
1 Root		K		1 - 1
1.1 Root.Client		K	..8	1 - 1
Client				
Identifier of the client where the operation is processed in AC.				
1.2 Root.User		O	..35	0 - 1
User				
AC-user under whose name the declaration is being imported and may be send to customs.				
1.3 Root.CountryOfLodgement		K	2	1 - 1
Country of lodgement				
ISO code of the country in which the operation is registered.				
Permitted values:				
DE		This import Interface may only be used for country of lodgement 'DE'		
1.4 Root.OperationDomain		K	..35	1 - 1
Operation domain				
Identifier for the process of the operation in AC. The country of lodgement, the operation domain and the operation type classify it.				
Permitted values:				
AES		Operation domain 'AES'		
1.5 Root.OperationType		K	..50	1 - 1
Operation type				
Identifier for the operation.				
Permitted values:				
Ergaenzende/ersetzende Anmeldung zur Ausfuhr		Operation type 'Ergaenzende/ersetzende Anmeldung zur Ausfuhr'		
1.6 Root.ID		O	..	0 - 1
ID				
For updating processes: ID is the transaction number created by AC after a transaction is registered. If the declaration is to be updated via the interface by ID, the field is allowed to be sent.				
1.7 Root.ReferenceNumber		O	..50	0 - 1
Reference number				
The reference number is the internal reference number of the declaration.				
This number needs to be unique for all processes of the same classification (Combination of country of lodgement, operation domain and operation type).				
1.8 Root.AdditionalReferenceNumber		O	..50	0 - 1
Additional reference number				
An additional reference number that can be used for the technical identification of the transaction. (not mandatory)				
1.9 Root.StatusNotificationEmail		O	..255	0 - 1
Status notification				
Use of the e-mail function in Advantage Customs is required. An email address is provided that is used for status notifications for the customs declaration. The configured e-mail settings in Advantage Customs are considered.				
1.10 Root.Meta		K		1 - 1
Meta				
The following elements define the processing of the transaction.				
1.10.1 Root.Meta.Operation		K	..	1 - 1
Operation				
Specification of the processing in AC.				
Permitted values:				
0		simulation of an import including validation (nothing will be stored in AC)		
1		import of the operation into AC without business validation and dispatch		
5		import of the operation into AC including business validation and dispatch (in case of validation errors the operation will still be stored in AC)		
7		import of the operation into AC including business validation and dispatch (in case of validation errors the operation will NOT be stored in AC)		

Identifier		Required/Optional	Format	Iteration
1.10.2 Root.Meta.ReferenceType		0	..35	0 - 1
Reference type				
For updating processes: The reference type controls the update logic of the interface: If the element 'Root/ReferenceType' is not transmitted in the data set, it is always a new creation. If a reference type is transmitted, it is an update data set. The specified value controls which reference is used to determine the transaction to be updated in AC.				
The supported reference types are 'ID' and 'ReferenceNumber'.				
Permitted values:				
ID	ID Referencing via the unique technical ID of the transaction. The ID is assigned by AC when a new transaction is created. In order to control updates from the customer's system via this ID, the system must receive and save the ID (e.g. via receipt or export interfaces).			
ReferenceNumber	Reference number Referencing via the reference number of the transaction.			
1.10.3 Root.Meta.ShipmentNumber		0	..35	0 - 1
If a shipment number ist provided, a shipment (Sendung) will be created together with export entire data. If this shipment number already exists, this process will become the follow-up process for this shipment.				
1.11 Root.Transition		K		1 - 1
Transition				
Field which AC internally uses to identify the current type of transition. Usually it correlates to the type/name of the exchanged message.				
1.11.1 Root.Transition.TransitionType		K	9	1 - 1
Transition type				
Indication of the ATLAS message.				
Permitted values:				
E_EXP_ENT	The ATLAS message type must always be E_EXP_ENT.			
1.11.2 Root.Transition.MRN		0	18	0 - 1
MRN				
Indication of the master reference number (MRN) for this operation.				
1.11.3 Root.Transition.SupplementSubmissionDateAndTime		0	..	0 - 1
Supplement submission date and time				
Date and time of the supplement submission				
1.11.4 Root.Transition.SupplementSubmissionTimezone		0	..255	0 - 1
Supplement submission time zone				
Indication of the time zone				
IANA standard (https://www.iana.org/time-zones)				
1.11.5 Root.Transition.TotalAmountInvoiced		0	n....16,2	0 - 1
Total amount invoiced				
Invoiced amount of all goods.				
Note: In the case of free delivery, enter an invoiced amount of '0'.				
1.11.6 Root.Transition.InvoiceCurrency		0	3	0 - 1
Invoice currency				
ATLAS code list: C0352				
Currency of the invoice				
1.11.7 Root.Transition.CustomsOfficeOfSupplement		0	8	0 - 1
Customs office of supplement				
ATLAS code list: D0193				
Indication of the responsible customs office of supplement				
1.11.8 Root.Transition.Declarant		0		0 - 1
Declarant				
1.11.8.1 Root.Transition.Declarant.Code		0	..250	0 - 1
Code				
The reference code for the business partner master data in AC.				

Identifier	Required/Optional	Format	Iteration
1.11.8.2 Root.Transition.Declarant.IdentificationNumber	0	..17	0 - 1
Identification number Identification number / EORI number			
1.11.8.3 Root.Transition.Declarant.SubsidiaryNumber	0	..	0 - 1
Subsidiary number Number of the subsidiary of the contracutal partner, assigned by the German customs authority.			
1.11.9 Root.Transition.GoodsShipment	0		0 - 1
Goods shipment			
1.11.9.1 Root.Transition.GoodsShipment.NatureOfTransaction	0	..	0 - 1
Nature of transaction In this data field, the type of transaction (information from which certain clauses of the business contract become apparent) is to be indicated with the key number accordingly.			
1.11.9.2 Root.Transition.GoodsShipment.DeliveryTerms	0		0 - 1
Delivery terms Clauses of the business contract with details of the delivery terms.			
1.11.9.2.1 Root.Transition.GoodsShipment.DeliveryTerms.IncotermsCode	0	3	0 - 1
INCOTERM code ATLAS code list: CO090 Incoterm code			
1.11.9.2.2 Root.Transition.GoodsShipment.DeliveryTerms.UNLocode	0	..17	0 - 1
UN/LOCODE ATLAS code list: CO244 United Nations coding on location information for trade and transport			
1.11.9.2.3 Root.Transition.GoodsShipment.DeliveryTerms.Location	0	..35	0 - 1
Location United Nations coding on location information for trade and transport			
1.11.9.2.4 Root.Transition.GoodsShipment.DeliveryTerms.Country	0	2	0 - 1
Country ATLAS code list: CO248 Country code Note: The specification of the data field is required if the data field 'INCOTERMS code' is specified with a value not equal to 'XXX', but not the data field 'UN/LOCODE'.			
1.11.9.2.5 Root.Transition.GoodsShipment.DeliveryTerms.Text	0	..512	0 - 1
Text Description of delivery term Note: The specification of the data field is required and only allowed if the data field 'INCOTERMS code' is specified with the value 'XXX'.			
1.11.9.3 Root.Transition.GoodsShipment.PreviousDocument	0		0 - 99
Previous document Details of previous document			
1.11.9.3.1 Root.Transition.GoodsShipment.PreviousDocument.SequenceNumber	0	n....2	0 - 1
Sequence number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.9.3.2 Root.Transition.GoodsShipment.PreviousDocument.TypeAndQualifier	0	..8	0 - 1
Type and Qualifier ATLAS code list: IO931 Type and qualifier of previous document			
1.11.9.3.3 Root.Transition.GoodsShipment.PreviousDocument.ReferenceNumber	0	..70	0 - 1
Reference number Reference number of previous documents			

Identifier	Required/Optional	Format	Iteration
1.11.9.4 Root.Transition.GoodsShipment.Consignment	0		0 - 1
Consignment			
1.11.9.4.1 Root.Transition.GoodsShipment.Consignment.ContainerIndicator	0	..	0 - 1
Container indicator			
ATLAS code list: S0027			
Indication of the transport of the goods in containers.			
1.11.9.4.2 Root.Transition.GoodsShipment.Consignment.InlandModeOfTransport	0	..	0 - 1
Inland mode of transport			
ATLAS code list: C0018			
Indication of the inland mode of transport.			
1.11.9.4.3 Root.Transition.GoodsShipment.Consignment.ModeOfTransportAtTheBorder	0	..	0 - 1
Mode of transport at the border			
ATLAS code list: C0018			
Verkehrszweig des Beförderungsmittels, mit dem die Außengrenze des Zollgebietes der Union überschritten wird.			
1.11.9.4.4 Root.Transition.GoodsShipment.Consignment.Consignee	0		0 - 1
Consignee			
1.11.9.4.4.1 Root.Transition.GoodsShipment.Consignment.Consignee.Code	0	..250	0 - 1
Code			
The reference code for the business partner master data in AC.			
1.11.9.4.4.2 Root.Transition.GoodsShipment.Consignment.Consignee.IdentificationNumber	0	..17	0 - 1
Identification number			
Indication of the EORI number of the consignee			
1.11.9.4.4.3 Root.Transition.GoodsShipment.Consignment.Consignee.SubsidiaryNumber	0	..	0 - 1
Subsidiary number			
Number of the subsidiary of the consignee (stated by the German customs office)			
1.11.9.4.4.4 Root.Transition.GoodsShipment.Consignment.Consignee.Name	0	..70	0 - 1
Name			
Name or company name of the consignee			
1.11.9.4.4.5 Root.Transition.GoodsShipment.Consignment.Consignee.Address	0		0 - 1
Address			
Address data of consignee			
1.11.9.4.4.5.1 Root.Transition.GoodsShipment.Consignment.Consignee.Address.StreetAndNumber	0	..70	0 - 1
Street and number			
1.11.9.4.4.5.2 Root.Transition.GoodsShipment.Consignment.Consignee.Address.Postcode	0	..17	0 - 1
Postcode			
1.11.9.4.4.5.3 Root.Transition.GoodsShipment.Consignment.Consignee.Address.City	0	..35	0 - 1
City			
1.11.9.4.4.5.4 Root.Transition.GoodsShipment.Consignment.Consignee.Address.Country	0	2	0 - 1
Country			
ATLAS code list: C0248			
Country code of the address of the consignee			
1.11.9.4.5 Root.Transition.GoodsShipment.Consignment.TransportEquipment	0		0 - 9999
Transport equipment			
1.11.9.4.5.1 Root.Transition.GoodsShipment.Consignment.TransportEquipment.SequenceNumber	0	n....4	0 - 1
Sequence number			
The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			

Identifier	Required/Optional	Format	Iteration
1.11.9.4.5.2 Root.Transition.GoodsShipment.Consignment.TransportEquipment.ContainerIdentificationNumber	0	..17	0 - 1
Container identification number Indication of the container number.			
1.11.9.4.5.3 Root.Transition.GoodsShipment.Consignment.TransportEquipment.GoodsReference	0		0 - 999
Goods reference Note: Indication of this data field if the data field 'Container number' is not indicated.			
1.11.9.4.5.3.1 Root.Transition.GoodsShipment.Consignment.TransportEquipment.GoodsReference.SequenceNumber	0	n....3	0 - 1
Sequence number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.9.4.5.3.2 Root.Transition.GoodsShipment.Consignment.TransportEquipment.GoodsReference.DeclarationGoodsItemNumber	0	n....3	0 - 1
Declaration goods item number Reference to the goods item number			
1.11.9.4.6 Root.Transition.GoodsShipment.Consignment.DepartureTransportMeans	0		0 - 999
Departure transport means			
1.11.9.4.6.1 Root.Transition.GoodsShipment.Consignment.DepartureTransportMeans.SequenceNumber	0	n....3	0 - 1
Sequence number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.9.4.6.2 Root.Transition.GoodsShipment.Consignment.DepartureTransportMeans.TypeOfIdentification	0	..	0 - 1
Type of identification ATLAS code list: C0750 Type of identification of the transport means at departure			
1.11.9.4.6.3 Root.Transition.GoodsShipment.Consignment.DepartureTransportMeans.IdentificationNumber	0	..35	0 - 1
Identification number Identify of vehicle License plate of vehicle			
1.11.9.4.6.4 Root.Transition.GoodsShipment.Consignment.DepartureTransportMeans.Nationality	0	2	0 - 1
Nationality ATLAS code list: C0165 Nationality of the means of transport			
1.11.9.4.7 Root.Transition.GoodsShipment.Consignment.ActiveBorderTransportMeans	0		0 - 1
Active border transport means			
1.11.9.4.7.1 Root.Transition.GoodsShipment.Consignment.ActiveBorderTransportMeans.TypeOfIdentification	0	..	0 - 1
Type of identification ATLAS code list: C0219 Type of identification of the transport means			
1.11.9.4.7.2 Root.Transition.GoodsShipment.Consignment.ActiveBorderTransportMeans.IdentificationNumber	0	..35	0 - 1
Identification number Identify of vehicle			
1.11.9.4.7.3 Root.Transition.GoodsShipment.Consignment.ActiveBorderTransportMeans.Nationality	0	2	0 - 1
Nationality ATLAS code list: C0165 Nationality of the means of transport			
1.11.9.5 Root.Transition.GoodsShipment.GoodsItem	0		0 - 999
Goods item			
1.11.9.5.1 Root.Transition.GoodsShipment.GoodsItem.SequenceNumber	0	n....3	0 - 1
Sequence number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			

Identifier	Required/Optional	Format	Iteration
1.11.9.5.2 Root.Transition.GoodsShipment.GoodsItem.StatisticalValue	0	n....16,2	0 - 1
Statistical value Statistic value of the declared goods			
1.11.9.5.3 Root.Transition.GoodsShipment.GoodsItem.NatureOfTransaction	0	..	0 - 1
Nature of transaction In this data field, the type of transaction (information from which certain clauses of the business contract become apparent) is to be indicated with the key number accordingly.			
1.11.9.5.4 Root.Transition.GoodsShipment.GoodsItem.Consignee	0		0 - 1
Consignee			
1.11.9.5.4.1 Root.Transition.GoodsShipment.GoodsItem.Consignee.Code	0	..250	0 - 1
Code The reference code for the business partner master data in AC.			
1.11.9.5.4.2 Root.Transition.GoodsShipment.GoodsItem.Consignee.IdentificationNumber	0	..17	0 - 1
Identification number Indication of the EORI number of the consignee			
1.11.9.5.4.3 Root.Transition.GoodsShipment.GoodsItem.Consignee.SubsidiaryNumber	0	..	0 - 1
Subsidiary number Number of the subsidiary of the consignee (stated by the German customs office)			
1.11.9.5.4.4 Root.Transition.GoodsShipment.GoodsItem.Consignee.Name	0	..70	0 - 1
Name Name or company name of the consignee			
1.11.9.5.4.5 Root.Transition.GoodsShipment.GoodsItem.Consignee.Address	0		0 - 1
Address Adress data of consignee			
1.11.9.5.4.5.1 Root.Transition.GoodsShipment.GoodsItem.Consignee.Address.StreetAndNumber	0	..70	0 - 1
Street and number			
1.11.9.5.4.5.2 Root.Transition.GoodsShipment.GoodsItem.Consignee.Address.Postcode	0	..17	0 - 1
Postcode			
1.11.9.5.4.5.3 Root.Transition.GoodsShipment.GoodsItem.Consignee.Address.City	0	..35	0 - 1
City			
1.11.9.5.4.5.4 Root.Transition.GoodsShipment.GoodsItem.Consignee.Address.Country	0	2	0 - 1
Country ATLAS code list: C0248 Country code of the address of the consignee			
1.11.9.5.5 Root.Transition.GoodsShipment.GoodsItem.CountryOfOrigin	0	2	0 - 1
Country of origin ATLAS code list: C0248 Country code of the origin country			
1.11.9.5.6 Root.Transition.GoodsShipment.GoodsItem.RegionOfDispatch	0	..9	0 - 1
Region of dispatch Code of the origin federal state of the goods			
1.11.9.5.7 Root.Transition.GoodsShipment.GoodsItem.SupplementaryUnits	0	n....16,6	0 - 1
Supplementary units Supplementary unites depends on the commodity code.			
1.11.9.5.8 Root.Transition.GoodsShipment.GoodsItem.PreviousDocument	0		0 - 99
Previous docuement			
1.11.9.5.8.1 Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.SequenceNumber	0	n....2	0 - 1
Sequence number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			

Identifier	Required/Optional	Format	Iteration
1.11.9.5.8.2 Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.TypeAndQualifier	0	..8	0 - 1
Type and qualifier ATLAS code list: IO932 Type and qualifier of previous document			
1.11.9.5.8.3 Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.ReferenceNumber	0	..70	0 - 1
Reference number Reference number of previous documents			
1.11.9.5.8.4 Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.GoodsItemNumber	0	n....5	0 - 1
Goods item number Reference to the goods item number			
1.11.9.5.8.5 Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.MeasurementUnitAndQualifier	0	..4	0 - 1
Measurement unit and qualifier ATLAS code list: C0349 Unit of measurement for the quantity of goods to be transferred from the previous procedure.			
1.11.9.5.8.6 Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.Quantity	0	n....16,6	0 - 1
Quantity Quantity of goods to be transferred from the previous procedure.			
1.11.9.5.8.7 Root.Transition.GoodsShipment.GoodsItem.PreviousDocument.ComplementOfInformation	0	..35	0 - 1
Complement of information Additional textual description of the previous document.			