

Key: NCTS_DE_IN_XML_AI
XSD: interfaceDescription_NCTS_DE_IN_XML_AI - Ausgehender Versand - 1.10.0.xsd
Document-Version: interfaceDescription_NCTS_DE_IN_XML_AI - Ausgehender Versand - 1.10.0
Notes:

1	Root
1.1	Root.Client
1.2	Root.User
1.3	Root.CountryOfLodgement
1.4	Root.OperationDomain
1.5	Root.OperationType
1.6	Root.ID
1.7	Root.ReferenceNumber
1.8	Root.AdditionalReferenceNumber
1.9	Root.StatusNotificationEmail
1.10	Root.Meta
1.10.1	Root.Meta.Operation
1.10.2	Root.Meta.ReferenceType
1.10.3	Root.Meta.CopyTemplate
1.10.3.1	Root.Meta.CopyTemplate.Reference
1.10.3.2	Root.Meta.CopyTemplate.ReferenceType
1.10.4	Root.Meta.ShipmentNumber
1.10.5	Root.Meta.PreventFloodingArticleData
1.10.6	Root.Meta.TransferAuthorisationFromMasterData
1.10.7	Root.Meta.PerformUserDefinedActions
1.10.8	Root.Meta.PositionReference
1.10.8.1	Root.Meta.PositionReference.SequenceNumberHouseConsignment
1.10.8.2	Root.Meta.PositionReference.SequenceNumberConsignmentItem
1.10.8.3	Root.Meta.PositionReference.StockSelection
1.10.8.3.1	Root.Meta.PositionReference.StockSelection.RegistrationID
1.10.8.3.2	Root.Meta.PositionReference.StockSelection.WarehouseAccountNumber
1.10.8.3.3	Root.Meta.PositionReference.StockSelection.LvsID
1.10.8.3.4	Root.Meta.PositionReference.StockSelection.DisposerWarehouse
1.10.8.3.5	Root.Meta.PositionReference.StockSelection.ArticleNumber
1.10.8.3.6	Root.Meta.PositionReference.StockSelection.StorageProcedureCode
1.10.8.3.7	Root.Meta.PositionReference.StockSelection.StorageLocationCode
1.10.8.3.8	Root.Meta.PositionReference.StockSelection.AuthorisationReferenceNumber
1.10.8.3.9	Root.Meta.PositionReference.StockSelection.AdditionalReferenceNumber
1.10.9	Root.Meta.CalculateGuaranteeByConsignmentsItemPositions
1.10.10	Root.Meta.CalculateGuaranteeByTotalInvoiceAmount
1.10.11	Root.Meta.UseFactorFromGRN
1.10.12	Root.Meta.CustomFactorInPercent
1.11	Root.Transition
1.11.1	Root.Transition.TransitionType
1.11.2	Root.Transition.LRN
1.11.3	Root.Transition.DeclarationType
1.11.4	Root.Transition.TransitDeclarationType
1.11.5	Root.Transition.TIRCarnetNumber
1.11.6	Root.Transition.LimitDate
1.11.7	Root.Transition.Security
1.11.8	Root.Transition.ReducedDatasetIndicator
1.11.9	Root.Transition.SpecificCircumstanceIndicator
1.11.10	Root.Transition.BindingItinerary
1.11.11	Root.Transition.Authorisation
1.11.11.1	Root.Transition.Authorisation.SequenceNumber
1.11.11.2	Root.Transition.Authorisation.Type
1.11.11.3	Root.Transition.Authorisation.ReferenceNumber
1.11.12	Root.Transition.CustomsOfficeOfDeparture
1.11.13	Root.Transition.CustomsOfficeOfDestinationDeclared
1.11.14	Root.Transition.CustomsOfficeOfTransitDeclared
1.11.14.1	Root.Transition.CustomsOfficeOfTransitDeclared.SequenceNumber
1.11.14.2	Root.Transition.CustomsOfficeOfTransitDeclared.ReferenceNumber
1.11.14.3	Root.Transition.CustomsOfficeOfTransitDeclared.ArrivalDateAndTimeEstimated
1.11.14.4	Root.Transition.CustomsOfficeOfTransitDeclared.ArrivalDateAndTimeEstimatedTimezone
1.11.15	Root.Transition.CustomsOfficeOfExitForTransitDeclared
1.11.15.1	Root.Transition.CustomsOfficeOfExitForTransitDeclared.SequenceNumber

1.11.15.2	Root.Transition.CustomsOfficeOfExitForTransitDeclared.ReferenceNumber
1.11.16	Root.Transition.HolderOfTheTransitProcedure
1.11.16.1	Root.Transition.HolderOfTheTransitProcedure.Code
1.11.16.2	Root.Transition.HolderOfTheTransitProcedure.IdentificationNumber
1.11.16.3	Root.Transition.HolderOfTheTransitProcedure.TIRHolderIdentificationNumber
1.11.16.4	Root.Transition.HolderOfTheTransitProcedure.Name
1.11.16.5	Root.Transition.HolderOfTheTransitProcedure.Address
1.11.16.5.1	Root.Transition.HolderOfTheTransitProcedure.Address.StreetAndNumber
1.11.16.5.2	Root.Transition.HolderOfTheTransitProcedure.Address.Postcode
1.11.16.5.3	Root.Transition.HolderOfTheTransitProcedure.Address.City
1.11.16.5.4	Root.Transition.HolderOfTheTransitProcedure.Address.Country
1.11.16.6	Root.Transition.HolderOfTheTransitProcedure.ContactPerson
1.11.16.6.1	Root.Transition.HolderOfTheTransitProcedure.ContactPerson.Name
1.11.16.6.2	Root.Transition.HolderOfTheTransitProcedure.ContactPerson.PhoneNumber
1.11.16.6.3	Root.Transition.HolderOfTheTransitProcedure.ContactPerson.EmailAddress
1.11.17	Root.Transition.Representative
1.11.17.1	Root.Transition.Representative.Code
1.11.17.2	Root.Transition.Representative.IdentificationNumber
1.11.17.3	Root.Transition.Representative.ContactPerson
1.11.17.3.1	Root.Transition.Representative.ContactPerson.Name
1.11.17.3.2	Root.Transition.Representative.ContactPerson.PhoneNumber
1.11.17.3.3	Root.Transition.Representative.ContactPerson.EmailAddress
1.11.18	Root.Transition.Guarantee
1.11.18.1	Root.Transition.Guarantee.SequenceNumber
1.11.18.2	Root.Transition.Guarantee.GuaranteeType
1.11.18.3	Root.Transition.Guarantee.OtherGuaranteeReference
1.11.18.4	Root.Transition.Guarantee.GuaranteeReference
1.11.18.4.1	Root.Transition.Guarantee.GuaranteeReference.SequenceNumber
1.11.18.4.2	Root.Transition.Guarantee.GuaranteeReference.GRN
1.11.18.4.3	Root.Transition.Guarantee.GuaranteeReference.AccessCode
1.11.18.4.4	Root.Transition.Guarantee.GuaranteeReference.TotalInvoiceAmount
1.11.18.4.5	Root.Transition.Guarantee.GuaranteeReference.TotalInvoiceCurrency
1.11.18.4.6	Root.Transition.Guarantee.GuaranteeReference.AmountToBeCovered
1.11.18.4.7	Root.Transition.Guarantee.GuaranteeReference.Currency
1.11.19	Root.Transition.Consignment
1.11.19.1	Root.Transition.Consignment.CountryOfDispatch
1.11.19.2	Root.Transition.Consignment.CountryOfDestination
1.11.19.3	Root.Transition.Consignment.ContainerIndicator
1.11.19.4	Root.Transition.Consignment.InlandModeOfTransport
1.11.19.5	Root.Transition.Consignment.ModeOfTransportAtTheBorder
1.11.19.6	Root.Transition.Consignment.GrossMass
1.11.19.7	Root.Transition.Consignment.ReferenceNumberUCR
1.11.19.8	Root.Transition.Consignment.Carrier
1.11.19.8.1	Root.Transition.Consignment.Carrier.Code
1.11.19.8.2	Root.Transition.Consignment.Carrier.IdentificationNumber
1.11.19.8.3	Root.Transition.Consignment.Carrier.SubsidiaryNumber
1.11.19.8.4	Root.Transition.Consignment.Carrier.ContactPerson
1.11.19.8.4.1	Root.Transition.Consignment.Carrier.ContactPerson.Name
1.11.19.8.4.2	Root.Transition.Consignment.Carrier.ContactPerson.PhoneNumber
1.11.19.8.4.3	Root.Transition.Consignment.Carrier.ContactPerson.EmailAddress
1.11.19.9	Root.Transition.Consignment.Consignor
1.11.19.9.1	Root.Transition.Consignment.Consignor.Code
1.11.19.9.2	Root.Transition.Consignment.Consignor.IdentificationNumber
1.11.19.9.3	Root.Transition.Consignment.Consignor.SubsidiaryNumber
1.11.19.9.4	Root.Transition.Consignment.Consignor.Name
1.11.19.9.5	Root.Transition.Consignment.Consignor.Address
1.11.19.9.5.1	Root.Transition.Consignment.Consignor.Address.StreetAndNumber
1.11.19.9.5.2	Root.Transition.Consignment.Consignor.Address.Postcode
1.11.19.9.5.3	Root.Transition.Consignment.Consignor.Address.City
1.11.19.9.5.4	Root.Transition.Consignment.Consignor.Address.Country
1.11.19.9.6	Root.Transition.Consignment.Consignor.ContactPerson

1.11.19.9.6.1	Root.Transition.Consignment.Consignor.ContactPerson.Name
1.11.19.9.6.2	Root.Transition.Consignment.Consignor.ContactPerson.PhoneNumber
1.11.19.9.6.3	Root.Transition.Consignment.Consignor.ContactPerson.EMailAddress
1.11.19.10	Root.Transition.Consignment.Consignee
1.11.19.10.1	Root.Transition.Consignment.Consignee.Code
1.11.19.10.2	Root.Transition.Consignment.Consignee.IdentificationNumber
1.11.19.10.3	Root.Transition.Consignment.Consignee.SubsidiaryNumber
1.11.19.10.4	Root.Transition.Consignment.Consignee.Name
1.11.19.10.5	Root.Transition.Consignment.Consignee.Address
1.11.19.10.5.1	Root.Transition.Consignment.Consignee.Address.StreetAndNumber
1.11.19.10.5.2	Root.Transition.Consignment.Consignee.Address.Postcode
1.11.19.10.5.3	Root.Transition.Consignment.Consignee.Address.City
1.11.19.10.5.4	Root.Transition.Consignment.Consignee.Address.Country
1.11.19.10.6	Root.Transition.Consignment.Consignee.ContactPerson
1.11.19.10.6.1	Root.Transition.Consignment.Consignee.ContactPerson.Name
1.11.19.10.6.2	Root.Transition.Consignment.Consignee.ContactPerson.PhoneNumber
1.11.19.10.6.3	Root.Transition.Consignment.Consignee.ContactPerson.EMailAddress
1.11.19.11	Root.Transition.Consignment.AdditionalSupplyChainActor
1.11.19.11.1	Root.Transition.Consignment.AdditionalSupplyChainActor.SequenceNumber
1.11.19.11.2	Root.Transition.Consignment.AdditionalSupplyChainActor.Code
1.11.19.11.3	Root.Transition.Consignment.AdditionalSupplyChainActor.Role
1.11.19.11.4	Root.Transition.Consignment.AdditionalSupplyChainActor.IdentificationNumber
1.11.19.12	Root.Transition.Consignment.TransportEquipment
1.11.19.12.1	Root.Transition.Consignment.TransportEquipment.SequenceNumber
1.11.19.12.2	Root.Transition.Consignment.TransportEquipment.ContainerIdentificationNumber
1.11.19.12.3	Root.Transition.Consignment.TransportEquipment.NumberOfSeals
1.11.19.12.4	Root.Transition.Consignment.TransportEquipment.Seal
1.11.19.12.4.1	Root.Transition.Consignment.TransportEquipment.Seal.SequenceNumber
1.11.19.12.4.2	Root.Transition.Consignment.TransportEquipment.Seal.Identifier
1.11.19.12.5	Root.Transition.Consignment.TransportEquipment.GoodsReference
1.11.19.12.5.1	Root.Transition.Consignment.TransportEquipment.GoodsReference.SequenceNumber
1.11.19.12.5.2	Root.Transition.Consignment.TransportEquipment.GoodsReference.DeclarationGoodsItemNumber
1.11.19.13	Root.Transition.Consignment.LocationOfGoods
1.11.19.13.1	Root.Transition.Consignment.LocationOfGoods.TypeOfLocation
1.11.19.13.2	Root.Transition.Consignment.LocationOfGoods.QualifierOfIdentification
1.11.19.13.3	Root.Transition.Consignment.LocationOfGoods.AdditionalIdentifier
1.11.19.13.4	Root.Transition.Consignment.LocationOfGoods.ContactPerson
1.11.19.13.4.1	Root.Transition.Consignment.LocationOfGoods.ContactPerson.Name
1.11.19.13.4.2	Root.Transition.Consignment.LocationOfGoods.ContactPerson.PhoneNumber
1.11.19.13.4.3	Root.Transition.Consignment.LocationOfGoods.ContactPerson.EMailAddress
1.11.19.14	Root.Transition.Consignment.DepartureTransportMeans
1.11.19.14.1	Root.Transition.Consignment.DepartureTransportMeans.SequenceNumber
1.11.19.14.2	Root.Transition.Consignment.DepartureTransportMeans.TypeOfIdentification
1.11.19.14.3	Root.Transition.Consignment.DepartureTransportMeans.IdentificationNumber
1.11.19.14.4	Root.Transition.Consignment.DepartureTransportMeans.Nationality
1.11.19.15	Root.Transition.Consignment.CountryOfRoutingOfConsignment
1.11.19.15.1	Root.Transition.Consignment.CountryOfRoutingOfConsignment.SequenceNumber
1.11.19.15.2	Root.Transition.Consignment.CountryOfRoutingOfConsignment.Country
1.11.19.16	Root.Transition.Consignment.ActiveBorderTransportMeans
1.11.19.16.1	Root.Transition.Consignment.ActiveBorderTransportMeans.SequenceNumber
1.11.19.16.2	Root.Transition.Consignment.ActiveBorderTransportMeans.TypeOfIdentification
1.11.19.16.3	Root.Transition.Consignment.ActiveBorderTransportMeans.IdentificationNumber
1.11.19.16.4	Root.Transition.Consignment.ActiveBorderTransportMeans.Nationality
1.11.19.16.5	Root.Transition.Consignment.ActiveBorderTransportMeans.ConveyanceReferenceNumber
1.11.19.16.6	Root.Transition.Consignment.ActiveBorderTransportMeans.CustomsOfficeAtBorderDeclared
1.11.19.17	Root.Transition.Consignment.PlaceOfLoading
1.11.19.17.1	Root.Transition.Consignment.PlaceOfLoading.Country
1.11.19.17.2	Root.Transition.Consignment.PlaceOfLoading.Location
1.11.19.18	Root.Transition.Consignment.PlaceOfUnloading
1.11.19.18.1	Root.Transition.Consignment.PlaceOfUnloading.Country
1.11.19.18.2	Root.Transition.Consignment.PlaceOfUnloading.Location

1.11.19.19	Root.Transition.Consignment.PreviousDocument
1.11.19.19.1	Root.Transition.Consignment.PreviousDocument.SequenceNumber
1.11.19.19.2	Root.Transition.Consignment.PreviousDocument.Type
1.11.19.19.3	Root.Transition.Consignment.PreviousDocument.ReferenceNumber
1.11.19.19.4	Root.Transition.Consignment.PreviousDocument.ComplementOfInformation
1.11.19.20	Root.Transition.Consignment.SupportingDocument
1.11.19.20.1	Root.Transition.Consignment.SupportingDocument.SequenceNumber
1.11.19.20.2	Root.Transition.Consignment.SupportingDocument.Type
1.11.19.20.3	Root.Transition.Consignment.SupportingDocument.ReferenceNumber
1.11.19.20.4	Root.Transition.Consignment.SupportingDocument.DocumentLineItemNumber
1.11.19.20.5	Root.Transition.Consignment.SupportingDocument.ComplementOfInformation
1.11.19.21	Root.Transition.Consignment.TransportDocument
1.11.19.21.1	Root.Transition.Consignment.TransportDocument.SequenceNumber
1.11.19.21.2	Root.Transition.Consignment.TransportDocument.Type
1.11.19.21.3	Root.Transition.Consignment.TransportDocument.ReferenceNumber
1.11.19.22	Root.Transition.Consignment.AdditionalReference
1.11.19.22.1	Root.Transition.Consignment.AdditionalReference.SequenceNumber
1.11.19.22.2	Root.Transition.Consignment.AdditionalReference.Type
1.11.19.22.3	Root.Transition.Consignment.AdditionalReference.ReferenceNumber
1.11.19.23	Root.Transition.Consignment.AdditionalInformation
1.11.19.23.1	Root.Transition.Consignment.AdditionalInformation.SequenceNumber
1.11.19.23.2	Root.Transition.Consignment.AdditionalInformation.Code
1.11.19.23.3	Root.Transition.Consignment.AdditionalInformation.Text
1.11.19.24	Root.Transition.Consignment.PaymentMethodTransport
1.11.19.25	Root.Transition.Consignment.HouseConsignment
1.11.19.25.1	Root.Transition.Consignment.HouseConsignment.SequenceNumber
1.11.19.25.2	Root.Transition.Consignment.HouseConsignment.CountryOfDispatch
1.11.19.25.3	Root.Transition.Consignment.HouseConsignment.CountryOfDestination
1.11.19.25.4	Root.Transition.Consignment.HouseConsignment.GrossMass
1.11.19.25.5	Root.Transition.Consignment.HouseConsignment.ReferenceNumberUCR
1.11.19.25.6	Root.Transition.Consignment.HouseConsignment.Consignor
1.11.19.25.6.1	Root.Transition.Consignment.HouseConsignment.Consignor.Code
1.11.19.25.6.2	Root.Transition.Consignment.HouseConsignment.Consignor.IdentificationNumber
1.11.19.25.6.3	Root.Transition.Consignment.HouseConsignment.Consignor.SubsidiaryNumber
1.11.19.25.6.4	Root.Transition.Consignment.HouseConsignment.Consignor.Name
1.11.19.25.6.5	Root.Transition.Consignment.HouseConsignment.Consignor.Address
1.11.19.25.6.5.1	Root.Transition.Consignment.HouseConsignment.Consignor.Address.StreetAndNumber
1.11.19.25.6.5.2	Root.Transition.Consignment.HouseConsignment.Consignor.Address.Postcode
1.11.19.25.6.5.3	Root.Transition.Consignment.HouseConsignment.Consignor.Address.City
1.11.19.25.6.5.4	Root.Transition.Consignment.HouseConsignment.Consignor.Address.Country
1.11.19.25.6.6	Root.Transition.Consignment.HouseConsignment.Consignor.ContactPerson
1.11.19.25.6.6.1	Root.Transition.Consignment.HouseConsignment.Consignor.ContactPerson.Name
1.11.19.25.6.6.2	Root.Transition.Consignment.HouseConsignment.Consignor.ContactPerson.PhoneNumber
1.11.19.25.6.6.3	Root.Transition.Consignment.HouseConsignment.Consignor.ContactPerson.EmailAddress
1.11.19.25.7	Root.Transition.Consignment.HouseConsignment.Consignee
1.11.19.25.7.1	Root.Transition.Consignment.HouseConsignment.Consignee.Code
1.11.19.25.7.2	Root.Transition.Consignment.HouseConsignment.Consignee.IdentificationNumber
1.11.19.25.7.3	Root.Transition.Consignment.HouseConsignment.Consignee.SubsidiaryNumber
1.11.19.25.7.4	Root.Transition.Consignment.HouseConsignment.Consignee.Name
1.11.19.25.7.5	Root.Transition.Consignment.HouseConsignment.Consignee.Address
1.11.19.25.7.5.1	Root.Transition.Consignment.HouseConsignment.Consignee.Address.StreetAndNumber
1.11.19.25.7.5.2	Root.Transition.Consignment.HouseConsignment.Consignee.Address.Postcode
1.11.19.25.7.5.3	Root.Transition.Consignment.HouseConsignment.Consignee.Address.City
1.11.19.25.7.5.4	Root.Transition.Consignment.HouseConsignment.Consignee.Address.Country
1.11.19.25.7.6	Root.Transition.Consignment.HouseConsignment.Consignee.ContactPerson
1.11.19.25.7.6.1	Root.Transition.Consignment.HouseConsignment.Consignee.ContactPerson.Name
1.11.19.25.7.6.2	Root.Transition.Consignment.HouseConsignment.Consignee.ContactPerson.PhoneNumber
1.11.19.25.7.6.3	Root.Transition.Consignment.HouseConsignment.Consignee.ContactPerson.EmailAddress
1.11.19.25.8	Root.Transition.Consignment.HouseConsignment.AdditionalSupplyChainActor
1.11.19.25.8.1	Root.Transition.Consignment.HouseConsignment.AdditionalSupplyChainActor.SequenceNumber
1.11.19.25.8.2	Root.Transition.Consignment.HouseConsignment.AdditionalSupplyChainActor.Role

1.11.19.25.8.3	Root.Transition.Consignment.HouseConsignment.AdditionalSupplyChainActor.Code
1.11.19.25.8.4	Root.Transition.Consignment.HouseConsignment.AdditionalSupplyChainActor.IdentificationNumber
1.11.19.25.9	Root.Transition.Consignment.HouseConsignment.PreviousDocument
1.11.19.25.9.1	Root.Transition.Consignment.HouseConsignment.PreviousDocument.SequenceNumber
1.11.19.25.9.2	Root.Transition.Consignment.HouseConsignment.PreviousDocument.Type
1.11.19.25.9.3	Root.Transition.Consignment.HouseConsignment.PreviousDocument.ReferenceNumber
1.11.19.25.9.4	Root.Transition.Consignment.HouseConsignment.PreviousDocument.ComplementOfInformation
1.11.19.25.10	Root.Transition.Consignment.HouseConsignment.SupportingDocument
1.11.19.25.10.1	Root.Transition.Consignment.HouseConsignment.SupportingDocument.SequenceNumber
1.11.19.25.10.2	Root.Transition.Consignment.HouseConsignment.SupportingDocument.Type
1.11.19.25.10.3	Root.Transition.Consignment.HouseConsignment.SupportingDocument.ReferenceNumber
1.11.19.25.10.4	Root.Transition.Consignment.HouseConsignment.SupportingDocument.DocumentLineNumber
1.11.19.25.10.5	Root.Transition.Consignment.HouseConsignment.SupportingDocument.ComplementOfInformation
1.11.19.25.11	Root.Transition.Consignment.HouseConsignment.TransportDocument
1.11.19.25.11.1	Root.Transition.Consignment.HouseConsignment.TransportDocument.SequenceNumber
1.11.19.25.11.2	Root.Transition.Consignment.HouseConsignment.TransportDocument.Type
1.11.19.25.11.3	Root.Transition.Consignment.HouseConsignment.TransportDocument.ReferenceNumber
1.11.19.25.12	Root.Transition.Consignment.HouseConsignment.AdditionalReference
1.11.19.25.12.1	Root.Transition.Consignment.HouseConsignment.AdditionalReference.SequenceNumber
1.11.19.25.12.2	Root.Transition.Consignment.HouseConsignment.AdditionalReference.Type
1.11.19.25.12.3	Root.Transition.Consignment.HouseConsignment.AdditionalReference.ReferenceNumber
1.11.19.25.13	Root.Transition.Consignment.HouseConsignment.AdditionalInformation
1.11.19.25.13.1	Root.Transition.Consignment.HouseConsignment.AdditionalInformation.SequenceNumber
1.11.19.25.13.2	Root.Transition.Consignment.HouseConsignment.AdditionalInformation.Code
1.11.19.25.13.3	Root.Transition.Consignment.HouseConsignment.AdditionalInformation.Text
1.11.19.25.14	Root.Transition.Consignment.HouseConsignment.PaymentMethodTransport
1.11.19.25.15	Root.Transition.Consignment.HouseConsignment.ConsignmentItem
1.11.19.25.15.1	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SequenceNumber
1.11.19.25.15.2	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.DeclarationType
1.11.19.25.15.3	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CountryOfDispatch
1.11.19.25.15.4	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CountryOfDestination
1.11.19.25.15.5	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.ReferenceNumberUCR
1.11.19.25.15.6	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee
1.11.19.25.15.6.1	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.Code
1.11.19.25.15.6.2	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.IdentificationNumber
1.11.19.25.15.6.3	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.SubsidiaryNumber
1.11.19.25.15.6.4	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.Name
1.11.19.25.15.6.5	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.Address
1.11.19.25.15.6.5.1	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.Address.StreetAndNumber
1.11.19.25.15.6.5.2	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.Address.Postcode
1.11.19.25.15.6.5.3	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.Address.City
1.11.19.25.15.6.5.4	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.Address.Country
1.11.19.25.15.6.6	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.ContactPerson
1.11.19.25.15.6.6.1	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.ContactPerson.Name
1.11.19.25.15.6.6.2	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.ContactPerson.PhoneNumber
1.11.19.25.15.6.6.3	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.ContactPerson.EmailAddress
1.11.19.25.15.7	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalSupplyChainActor
1.11.19.25.15.7.1	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalSupplyChainActor.SequenceNumber
1.11.19.25.15.7.2	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalSupplyChainActor.Role
1.11.19.25.15.7.3	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalSupplyChainActor.Code
1.11.19.25.15.7.4	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalSupplyChainActor.IdentificationNumber
1.11.19.25.15.8	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.DescriptionOfGoods
1.11.19.25.15.9	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CusCode
1.11.19.25.15.10	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CommodityCode
1.11.19.25.15.11	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.DangerousGoods
1.11.19.25.15.11.1	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.DangerousGoods.SequenceNumber
1.11.19.25.15.11.2	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.DangerousGoods.UNNumber
1.11.19.25.15.12	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.GrossMass
1.11.19.25.15.13	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.NetMass
1.11.19.25.15.14	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Packaging
1.11.19.25.15.14.1	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Packaging.SequenceNumber

1.11.19.25.15.14.2	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Packaging.TypeOfPackages
1.11.19.25.15.14.3	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Packaging.NumberOfPackages
1.11.19.25.15.14.4	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Packaging.ShippingMarks
1.11.19.25.15.14.5	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Packaging.PackageReference
1.11.19.25.15.15	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.PreviousDocument
1.11.19.25.15.15.1	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.PreviousDocument.SequenceNumber
1.11.19.25.15.15.2	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.PreviousDocument.Type
1.11.19.25.15.15.3	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.PreviousDocument.ReferenceNumber
1.11.19.25.15.15.4	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.PreviousDocument.GoodsItemNumber
1.11.19.25.15.15.5	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.PreviousDocument.ComplementOfInformation
1.11.19.25.15.16	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SupportingDocument
1.11.19.25.15.16.1	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SupportingDocument.SequenceNumber
1.11.19.25.15.16.2	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SupportingDocument.Type
1.11.19.25.15.16.3	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SupportingDocument.ReferenceNumber
1.11.19.25.15.16.4	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SupportingDocument.DocumentLineItemNumber
1.11.19.25.15.16.5	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SupportingDocument.ComplementOfInformation
1.11.19.25.15.17	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalReference
1.11.19.25.15.17.1	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalReference.SequenceNumber
1.11.19.25.15.17.2	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalReference.Type
1.11.19.25.15.17.3	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalReference.ReferenceNumber
1.11.19.25.15.18	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalInformation
1.11.19.25.15.18.1	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalInformation.SequenceNumber
1.11.19.25.15.18.2	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalInformation.Code
1.11.19.25.15.18.3	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalInformation.Text
1.11.19.25.15.19	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.PaymentMethodTransport
1.11.19.25.15.20	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration
1.11.19.25.15.20.1	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.IdentificationType
1.11.19.25.15.20.2	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference
1.11.19.25.15.20.2.1	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference.SequenceNumber
1.11.19.25.15.20.2.2	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference.IdentificationByKey
1.11.19.25.15.20.2.2.1	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference.IdentificationByKey.Type
1.11.19.25.15.20.2.2.2	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference.IdentificationByKey.ReferenceNumber
1.11.19.25.15.20.2.2.3	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference.IdentificationByKey.Custodian
1.11.19.25.15.20.2.2.3.1	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference.IdentificationByKey.Custodian.Code
1.11.19.25.15.20.2.2.3.2	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference.IdentificationByKey.Custodian.identificationNumber
1.11.19.25.15.20.2.3	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference.IdentificationByRegistrationNumber
1.11.19.25.15.20.2.3.1	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference.IdentificationByRegistrationNumber.MRN
1.11.19.25.15.20.2.3.2	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference.IdentificationByRegistrationNumber.RegistrationNumber
1.11.19.25.15.20.2.3.3	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference.IdentificationByRegistrationNumber.GoodsItemNumber
1.11.19.25.15.20.2.4	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference.NumberOfPackages
1.11.19.25.15.21	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing
1.11.19.25.15.21.1	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.LRN
1.11.19.25.15.21.2	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.Authorisation
1.11.19.25.15.21.2.1	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.Authorisation.Type
1.11.19.25.15.21.2.2	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.Authorisation.ReferenceNumber
1.11.19.25.15.21.3	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference
1.11.19.25.15.21.3.1	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.SequenceNumber
1.11.19.25.15.21.3.2	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.AccessViaATLAS
1.11.19.25.15.21.3.3	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.MRN

1.11.19.25.15.21.3.4	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.RegistrationNumber
1.11.19.25.15.21.3.5	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.GoodsItemNumber
1.11.19.25.15.21.3.6	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.UsualTreatment
1.11.19.25.15.21.3.7	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.Complement
1.11.19.25.15.21.3.8	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.CommodityCode
1.11.19.25.15.21.3.9	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.GoodsReduction
1.11.19.25.15.21.3.9.1	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.GoodsReduction.MeasurementUnitAndQualifier
1.11.19.25.15.21.3.9.2	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.GoodsReduction.Quantity
1.11.19.25.15.21.3.10	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.GoodsReductionAfterTreatment
1.11.19.25.15.21.3.10.1	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.GoodsReductionAfterTreatment.MeasurementUnitAndQualifier
1.11.19.25.15.21.3.10.2	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.GoodsReductionAfterTreatment.Quantity
1.11.19.25.15.22	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing
1.11.19.25.15.22.1	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing.SimplyGrantedAuthorisation
1.11.19.25.15.22.2	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing.Authorisation
1.11.19.25.15.22.2.1	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing.Authorisation.Type
1.11.19.25.15.22.2.2	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing.Authorisation.ReferenceNumber
1.11.19.25.15.22.3	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing.CustomsOfficeOfSupervision
1.11.19.25.15.22.4	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing.GoodsReference
1.11.19.25.15.22.4.1	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing.GoodsReference.SequenceNumber
1.11.19.25.15.22.4.2	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing.GoodsReference.AccessViaATLAS
1.11.19.25.15.22.4.3	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing.GoodsReference.MRN
1.11.19.25.15.22.4.4	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing.GoodsReference.RegistrationNumber
1.11.19.25.15.22.4.5	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing.GoodsReference.GoodsItemNumber
1.11.19.25.15.22.4.6	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing.GoodsReference.GoodsRelatedData
1.11.19.25.15.23	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalId
1.11.19.25.15.24	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.QuantityOfGoods
1.11.19.25.15.25	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.QuantityOfGoodsMeasurement
1.11.19.25.15.26	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.ArticleNumber
1.11.19.25.15.27	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InvoiceAmount
1.11.19.25.15.28	Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InvoiceCurrency

Identifier	Required/Optional	Format	Iteration
1 Root	K		1 - 1
1.1 Root.Client	K	..8	1 - 1
Client Identifier of the client where the operation is processed in AC.			
1.2 Root.User	O	..35	0 - 1
User AC-user under whose name the declaration is being imported and may be send to customs.			
1.3 Root.CountryOfLodgement	K	2	1 - 1
Country of lodgement ISO code of the country in which the operation is registered. Permitted values: 'DE'			
DE	This import Interface may only be used for country of lodgement 'DE'		
1.4 Root.OperationDomain	K	..35	1 - 1
Operation domain Identifier for the process of the operation in AC. The country of lodgement, the operation domain and the operation type classify it. Permitted values: 'NCTS'			
NCTS	Operation domain 'NCTS'		
1.5 Root.OperationType	K	..50	1 - 1
Operation type Identifier for the operation. Permitted values: 'Ausgehender Versand'			
Ausgehender Versand	Operation type 'Ausgehender Versand'		
1.6 Root.ID	O	..	0 - 1
ID For updating processes: ID is the transaction number created by AC after a transaction is registered. If the declaration is to be updated via the interface by ID, the field is allowed to be sent.			
1.7 Root.ReferenceNumber	O	..50	0 - 1
Reference number The reference number is the internal reference number of the declaration. This number needs to be unique for all processes of the same classification (Combination of country of lodgement, operation domain and operation type).			
1.8 Root.AdditionalReferenceNumber	O	..50	0 - 1
Additional reference number An additional reference number that can be used for the technical identification of the transaction. (not mandatory)			
1.9 Root.StatusNotificationEmail	O	..255	0 - 1
Status notification Use of the e-mail function in Advantage Customs is required. An email address is provided that is used for status notifications for the customs declaration. The configured e-mail settings in Advantage Customs are considered.			
1.10 Root.Meta	K		1 - 1
Meta The following elements define the processing of the transaction.			
1.10.1 Root.Meta.Operation	K	..	1 - 1
Operation Specification of the processing in AC. Permitted values: '0', '1', '5', '7'			
0	simulation of an import including validation (nothing will be stored in AC)		
1	import of the operation into AC without business validation and dispatch		
5	import of the operation into AC including business validation and dispatch (in case of validation errors the operation will still be stored in AC)		
7	import of the operation into AC including business validation and dispatch (in case of validation errors the operation will NOT be stored in AC)		

Interface description:	NCTS_DE_IN_XML_AI (XML) - Ausgehender Versand - 1.10.0	Creation date 01.06.2026 Created by AC-20-p20.010	Page 10 of 35
------------------------	--	--	---------------

Identifier	Required/Optional	Format	Iteration
1.10.2 Root.Meta.ReferenceType	0	..35	0 - 1
Reference type For updating processes: The reference type controls the update logic of the interface: If the element 'Root/ReferenceType' is not transmitted in the data set, it is always a new creation. If a reference type is transmitted, it is an update data set. The specified value controls which reference is used to determine the transaction to be updated in AC. The supported reference types are 'ID' and 'ReferenceNumber'. Permitted values: 'ID', 'ReferenceNumber'			
ID	ID Referencing via the unique technical ID of the transaction. The ID is assigned by AC when a new transaction is created. In order to control updates from the customer's system via this ID, the system must receive and save the ID (e.g. via receipt or export interfaces).		
ReferenceNumber	Reference number Referencing via the reference number of the transaction.		
1.10.3 Root.Meta.CopyTemplate	0		0 - 1
CopyTemplate The following elements define the references for copytemplates.			
1.10.3.1 Root.Meta.CopyTemplate.Reference	K	..50	1 - 1
Reference If contents are to be taken over from an AC copy template, the reference number of the copy template is indicated here.			
1.10.3.2 Root.Meta.CopyTemplate.ReferenceType	K	..35	1 - 1
Reference type The ID or ReferenceNumber must be entered as the Reference Type for the copy template. Permitted values: 'ID', 'ReferenceNumber'			
ID	ID Referencing via the unique technical ID of the transaction. The ID is assigned by AC when a new transaction is created. In order to control updates from the customer's system via this ID, the system must receive and save the ID (e.g. via receipt or export interfaces).		
ReferenceNumber	Reference number Referencing via the reference number of the transaction.		
1.10.4 Root.Meta.ShipmentNumber	0	..35	0 - 1
If a shipment number ist provided, a shipment (Sendung) will be created together with export data. If this shipment number already exists, this process will become the follow-up process for this shipment.			
1.10.5 Root.Meta.PreventFloodingArticleData	0		0 - 1
The field controls whether article master data is retrieved based on the provided article number. By default, the system retrieves the article master data automatically. If the indicator "true" is submitted in this field, the system does not retrieve article master data. Instead, the values provided in the interface are used as transmitted. If the indicator "false" or no field at all is submitted, the system uses the article number to retrieve and apply the corresponding article master data.			
1.10.6 Root.Meta.TransferAuthorisationFromMasterData	0		0 - 1
Transfer authorisation number from master data If the indicator "true" is submitted in this field, the authorisation number is identified on the basis of the business partner. Otherwise, the authorisation number must be submitted in the XML file.			
1.10.7 Root.Meta.PerformUserDefinedActions	0		0 - 1
Perform user defined actions If the indicator "true" is submitted in this field, user defined actions are performed as declared for the kind of business process. If the indicator is left out, user defined actions are performed only if declared in the configuration of the import interface. If the indicator "false" is submitted in this field, no user defined actions are performed regardless of the import interface configuration.			
1.10.8 Root.Meta.PositionReference	0		0 - 1999
Position reference			
1.10.8.1 Root.Meta.PositionReference.SequenceNumberHouseConsignment	K	n....4	1 - 1
The sequence number of the house consignment must be specified in order to allocate the stock account. Otherwise, the stock account cannot be assigned to the item.			
1.10.8.2 Root.Meta.PositionReference.SequenceNumberConsignmentItem	K	n....3	1 - 1
The sequence number of the consignment item must be specified in order to allocate the stock account. Otherwise, the stock account cannot be assigned to the item.			
1.10.8.3 Root.Meta.PositionReference.StockSelection	0		0 - 1
By specifying the following data fields, a stock account can be determined for a procedure transfer.			
1.10.8.3.1 Root.Meta.PositionReference.StockSelection.RegistrationID	0	..27	0 - 1
The MRN or ATLAS registration number with item number is provided for the registration ID. If this information is provided, no further fields are to be transmitted for stock selection. Only the procedure code (StorageProcedureCode) is permitted. Format: MRN/item number or ATLAS registration number/item number Example: 25DE5866BCMO053R7/1			

Identifier	Required/Optional	Format	Iteration
1.10.8.3.2 Root.Meta.PositionReference.StockSelection.WarehouseAccountNumber	0	..25	0 - 1
The corresponding warehouse stock can be assigned via the warehouse stock account number.			
1.10.8.3.3 Root.Meta.PositionReference.StockSelection.LvsID	0	..20	0 - 1
The LVS ID can be used as a reference from AC to determine the warehouse stock account.			
1.10.8.3.4 Root.Meta.PositionReference.StockSelection.DisposerWarehouse	0	..20	0 - 1
To determine the stock account, the disposer for the warehouse can be used as a filter.			
1.10.8.3.5 Root.Meta.PositionReference.StockSelection.ArticleNumber	0	..30	0 - 1
The article number of the warehouse stock can be used to determine the warehouse stock account.			
1.10.8.3.6 Root.Meta.PositionReference.StockSelection.StorageProcedureCode	K	..	1 - 1
The customs procedure must be indicated.			
Permitted values: '71'			
71	The customs procedure must be indicated.		
1.10.8.3.7 Root.Meta.PositionReference.StockSelection.StorageLocationCode	0	..100	0 - 1
The storage location can be used as a filter to determine the stock account.			
1.10.8.3.8 Root.Meta.PositionReference.StockSelection.AuthorisationReferenceNumber	0	..35	0 - 1
The authorization number from the warehouse must be indicated.			
1.10.8.3.9 Root.Meta.PositionReference.StockSelection.AdditionalReferenceNumber	0	..100	0 - 1
The additional reference number from the warehouse must be indicated.			
1.10.9 Root.Meta.CalculateGuaranteeByConsignmentsItemPositions	0		0 - 1
Indicator for calculating guarantee by consignments item positions			
Indication whether the guarantee amount is calculated based on the transmitted consignment item positions.			
If the indicator "true" is submitted in this field, the system calculates the guarantee using the itemlevel values provided in the interface.			
If the indicator "false" is submitted in this field, his calculation method is not applied.			
1.10.10 Root.Meta.CalculateGuaranteeByTotalInvoiceAmount	0		0 - 1
Indicator for calculating guarantee by total invoice amount			
Indication whether the guarantee amount is calculated based on the total invoice amount transmitted via the interface.			
If the indicator "true" is submitted in this field, the total invoice amount is used as the calculation basis.If the indicator "false" is submitted in this field, this calculation method is not applied.			
1.10.11 Root.Meta.UseFactorFromGRN	0		0 - 1
Indicator for using factor from GRN			
Indication whether the factor derived from the GRN is used for calculating the guarantee amount.			
If the indicator "true" is submitted in this field, the GRN factor is applied.			
If the indicator "false" is submitted in this field, the GRN factor is not used and other applicable factors may be considered.			
1.10.12 Root.Meta.CustomFactorInPercent	0	n....3,2	0 - 1
Custom factor in percent			
A custom percentage factor to be applied when calculating the guarantee amount. This factor is used only if the GRN factor is not applied.			
1.11 Root.Transition	0		0 - 1
Transition			
Field which AC internally uses to identify the current type of transition.			
Usually it correlates to the type/name of the exchanged message.			
1.11.1 Root.Transition.TransitionType	K	9	1 - 1
Transition type			
Indication of the ATLAS message.			
Permitted values: 'E_DEP_DAT'			
E_DEP_DAT	The ATLAS message type must always be E_DEP_DAT.		
1.11.2 Root.Transition.LRN	0	..22	0 - 1
LRN			
The local reference number is the reference number of the transit declaration. The LRN is assigned as a unique reference by the creator of the transit declaration.			

Identifier	Required/Optional	Format	Iteration
1.11.3 Root.Transition.DeclarationType	0	..5	0 - 1
Type of declaration ATLAS code list: S0231 A type of declaration must be indicated.			
1.11.4 Root.Transition.TransitDeclarationType	0	..	0 - 1
Type of transit declaration ATLAS code list: A0114 Indicate whether the normal procedure or the simplified procedure, with the use of special seals, is used. 00' = transit declaration under the normal procedure 10' = transit declaration under the simplified procedure without the use of special seals 11' = transit declaration for the simplified procedure with the use of special seals			
1.11.5 Root.Transition.TIRCarnetNumber	0	..12	0 - 1
Carnet TIR Number Identification number of the Carnet TIR process.			
1.11.6 Root.Transition.LimitDate	0	..	0 - 1
Date of representation Date of the end of the time for representation at the customs office of destination or at the place of the authorised consignee.			
1.11.7 Root.Transition.Security	0	..	0 - 1
Security ATLAS code list: C0217 If the transit declaration contains entry and/or exit summary declaration data, enter it here.			
1.11.8 Root.Transition.ReducedDatasetIndicator	0	..	0 - 1
Indicator for reduced Dataset ATLAS code list: S0027 A reduced data set may be declared if carriage is by sea or air.			
1.11.9 Root.Transition.SpecificCircumstanceIndicator	0	3	0 - 1
Indicator for specific circumstance ATLAS code list: C0296 Element identifying the particular circumstances invoked by the economic operator concerned, which is only related to an exit summary declaration. Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the indication of the value 'XXX' is not allowed.			
1.11.10 Root.Transition.BindingItinerary	0	..	0 - 1
Binding itinerary ATLAS code list: S0027 Indication of whether there is a predefined binding transport itinerary. Note: The specification of the value '1' is only permitted if the field 'Security' is specified with the value '0'.			
1.11.11 Root.Transition.Authorisation	0		0 - 9
Authorisation Authorisation issued by customs authorities			
1.11.11.1 Root.Transition.Authorisation.SequenceNumber	0	n....1	0 - 1
Sequence number The sequence number must be assigned per authorisation. The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.11.2 Root.Transition.Authorisation.Type	0	4	0 - 1
Type of authorisation ATLAS code list: S0235 Indication of the type of authorisation for one of the following simplifications: - authorised consignor (abbreviation 'ZV') - use of special seals - lodging of a transit declaration with reduced data set)			

Identifier	Required/Optional	Format	Iteration
1.11.11.3 Root.Transition.Authorisation.ReferenceNumber	0	..35	0 - 1
Authorisation reference number The authorisation reference number must be indicated.			
1.11.12 Root.Transition.CustomsOfficeOfDeparture	0	8	0 - 1
Customs Office of Departure Indication of customs office, where the goods need to be presented when they are transfered into transit procedure.			
1.11.13 Root.Transition.CustomsOfficeOfDestinationDeclared	0	8	0 - 1
Declared customs office of destination Indication of the customs office, where the goods must be presented for termination of the transit procedure.			
1.11.14 Root.Transition.CustomsOfficeOfTransitDeclared	0		0 - 9
Transit customs office Customs offices of transit designated for this transit operation.			
1.11.14.1 Root.Transition.CustomsOfficeOfTransitDeclared.SequenceNumber	0	n....1	0 - 1
The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.14.2 Root.Transition.CustomsOfficeOfTransitDeclared.ReferenceNumber	0	8	0 - 1
Reference number ATLAS code list: C0173 Reference number of the transit customs office			
1.11.14.3 Root.Transition.CustomsOfficeOfTransitDeclared.ArrivalDateAndTimeEstimated	0	..	0 - 1
Estimated time and date of arrival Expected format is "yyyy-MM-dd'T'HH:mm:ss", e.g. '2014-06-09T17:15:04'. Indication of estimated time of arrival at the transit customs office. Note: The specification of the data field is required if the data field 'Security' is specified with one of the values '1' or '3' and the first two digits of the data field 'Intended office of transit' are specified with a value of the code list C0147.			
1.11.14.4 Root.Transition.CustomsOfficeOfTransitDeclared.ArrivalDateAndTimeEstimatedTimezone	0	..255	0 - 1
Time zone IANA standard			
1.11.15 Root.Transition.CustomsOfficeOfExitForTransitDeclared	0		0 - 9
Declared Customs Office of Exit Note: The specification of the data is required and only permitted if the data field "Security" is specified with one of the values '2' or '3'.			
1.11.15.1 Root.Transition.CustomsOfficeOfExitForTransitDeclared.SequenceNumber	0	n....1	0 - 1
Sequence number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.15.2 Root.Transition.CustomsOfficeOfExitForTransitDeclared.ReferenceNumber	0	8	0 - 1
Reference number ATLAS code list: C0175 Reference number of the declared customs office of exit for transit.			
1.11.16 Root.Transition.HolderOfTheTransitProcedure	0		0 - 1
Holder of Transit Procedure Indication of the EORI number of the holder of the transit procedure.			
1.11.16.1 Root.Transition.HolderOfTheTransitProcedure.Code	0	..250	0 - 1
Code The reference code for the business partner master data in AC.			
1.11.16.2 Root.Transition.HolderOfTheTransitProcedure.IdentificationNumber	0	..17	0 - 1
Identification number Indication of the EORI number of the holder of the transit procedure.			
1.11.16.3 Root.Transition.HolderOfTheTransitProcedure.TIRHolderIdentificationNumber	0	..17	0 - 1
Identification number of the TIR-holder Indication of the indentification number of the TIR-holder.			

Identifier	Required/Optional	Format	Iteration
1.11.16.4 Root.Transition.HolderOfTheTransitProcedure.Name	0	..70	0 - 1
Name The name oder company name of the holder of the transit procedure.			
1.11.16.5 Root.Transition.HolderOfTheTransitProcedure.Address	0		0 - 1
Address Details of the address.			
1.11.16.5.1 Root.Transition.HolderOfTheTransitProcedure.Address.StreetAndNumber	0	..70	0 - 1
Street and number Street and number of the holder of the procedure.			
1.11.16.5.2 Root.Transition.HolderOfTheTransitProcedure.Address.Postcode	0	..17	0 - 1
Postcode Postcode of the holder of the procedure.			
1.11.16.5.3 Root.Transition.HolderOfTheTransitProcedure.Address.City	0	..35	0 - 1
City City of the holder of the procedure.			
1.11.16.5.4 Root.Transition.HolderOfTheTransitProcedure.Address.Country	0	2	0 - 1
Country ATLAS code list: C0248 Country code of the holder of the transit procedure.			
1.11.16.6 Root.Transition.HolderOfTheTransitProcedure.ContactPerson	0		0 - 1
Contact person Note: The indication of the contact person is necessary if representative is not going to be indicated.			
1.11.16.6.1 Root.Transition.HolderOfTheTransitProcedure.ContactPerson.Name	0	..70	0 - 1
Name of contact person Name of the contact person of the respresentative			
1.11.16.6.2 Root.Transition.HolderOfTheTransitProcedure.ContactPerson.PhoneNumber	0	..35	0 - 1
Phone number Phone number of the holder of the transit procedure.			
1.11.16.6.3 Root.Transition.HolderOfTheTransitProcedure.ContactPerson.EMailAddress	0	..256	0 - 1
E-mail address of contact person E-mail address of the contact person of the holder of the transit procedure.			
1.11.17 Root.Transition.Representative	0		0 - 1
Representative Direct (customs) representative of the holder of the procedure.			
1.11.17.1 Root.Transition.Representative.Code	0	..250	0 - 1
Code The reference code for the business partner master data in AC.			
1.11.17.2 Root.Transition.Representative.IdentificationNumber	0	..17	0 - 1
Identification number Indication of the EORI number of the representative.			
1.11.17.3 Root.Transition.Representative.ContactPerson	0		0 - 1
Contact person Contact person of the representative			
1.11.17.3.1 Root.Transition.Representative.ContactPerson.Name	0	..70	0 - 1
Name of contact person Name of the contact person of the representative.			

Identifier	Required/Optional	Format	Iteration
1.11.17.3.2 Root.Transition.Representative.ContactPerson.PhoneNumber	0	..35	0 - 1
Phone number of contact person			
Phone number of the contact person of the representative.			
1.11.17.3.3 Root.Transition.Representative.ContactPerson.EMailAddress	0	..256	0 - 1
E-mail address of contact person			
E-mail address of the contact person of the representative.			
1.11.18 Root.Transition.Guarantee	0		0 - 9
Details of the guarantee			
1.11.18.1 Root.Transition.Guarantee.SequenceNumber	0	n....1	0 - 1
Sequence number			
The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.18.2 Root.Transition.Guarantee.GuaranteeType	0	1	0 - 1
Type of guarantee			
ATLAS code list: S0251			
1.11.18.3 Root.Transition.Guarantee.OtherGuaranteeReference	0	..35	0 - 1
Other type of guarantee			
Certificate or proof that the guarantee has been provided to the AS in another form or that there is effectively no guarantee to be provided.			
1.11.18.4 Root.Transition.Guarantee.GuaranteeReference	0		0 - 99
Guarantee reference			
1.11.18.4.1 Root.Transition.Guarantee.GuaranteeReference.SequenceNumber	0	n....2	0 - 1
Sequence number			
The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.18.4.2 Root.Transition.Guarantee.GuaranteeReference.GRN	0	..24	0 - 1
GRN			
Indication of the guarantee reference number.			
1.11.18.4.3 Root.Transition.Guarantee.GuaranteeReference.AccessCode	0	..4	0 - 1
Guarantee access code			
Indication of the guarantee access code.			
1.11.18.4.4 Root.Transition.Guarantee.GuaranteeReference.TotalInvoiceAmount	0	n....16,2	0 - 1
Invoiced amount of all goods			
1.11.18.4.5 Root.Transition.Guarantee.GuaranteeReference.TotalInvoiceCurrency	0	3	0 - 1
Invoice currency			
ATLAS code list: C0352			
Currency for total amount			
1.11.18.4.6 Root.Transition.Guarantee.GuaranteeReference.AmountToBeCovered	0	n....16,2	0 - 1
Amount to be covered			
Coverage Amount stated in EUR.			
1.11.18.4.7 Root.Transition.Guarantee.GuaranteeReference.Currency	0	3	0 - 1
Currency			
Currency of the amount which will cover the guarantee			
1.11.19 Root.Transition.Consignment	0		0 - 1
Consignment			
1.11.19.1 Root.Transition.Consignment.CountryOfDispatch	0	2	0 - 1
Country of dispatch			
ATLAS code list: C0248			
Country code of the country of dispatch			

Identifier	Required/Optional	Format	Iteration
1.11.19.2 Root.Transition.Consignment.CountryOfDestination	0	2	0 - 1
Country of destination ATLAS code list: C0248 Country code of the country of destination			
1.11.19.3 Root.Transition.Consignment.ContainerIndicator	0	..	0 - 1
Indicator of container ATLAS code list: S0027 Indication of the transport of the goods in containers.			
1.11.19.4 Root.Transition.Consignment.InlandModeOfTransport	0	..	0 - 1
Inland mode of transport ATLAS code list: S0218 Indication of the inland mode of transport.			
1.11.19.5 Root.Transition.Consignment.ModeOfTransportAtTheBorder	0	..	0 - 1
Mode of transport at the border ATLAS code list: S0218 Indication of the mode of transport at the border of the european customs area.			
1.11.19.6 Root.Transition.Consignment.GrossMass	0	n....16,3	0 - 1
Gross mass Gross mass of the consignment in kilogram.			
1.11.19.7 Root.Transition.Consignment.ReferenceNumberUCR	0	..35	0 - 1
Reference number UCR Indication of an unique consignment reference.			
1.11.19.8 Root.Transition.Consignment.Carrier	0		0 - 1
Carrier The carrier is, in principle, the person who brings the goods across the frontier of the customs territory of the Union or who is responsible for the movement of the goods across the frontier of the customs territory of the Union.			
1.11.19.8.1 Root.Transition.Consignment.Carrier.Code	0	..250	0 - 1
Code The reference code for the business partner master data in AC.			
1.11.19.8.2 Root.Transition.Consignment.Carrier.IdentificationNumber	0	..17	0 - 1
Identification number Indication of the EORI number of the carrier.			
1.11.19.8.3 Root.Transition.Consignment.Carrier.SubsidiaryNumber	0	..	0 - 1
Subsidiary number The number of the subsidiary of the carrier (stated by the German customs office).			
1.11.19.8.4 Root.Transition.Consignment.Carrier.ContactPerson	0		0 - 1
Contact person of the carrier			
1.11.19.8.4.1 Root.Transition.Consignment.Carrier.ContactPerson.Name	0	..70	0 - 1
Name of contact person Name of the contact person of the carrier.			
1.11.19.8.4.2 Root.Transition.Consignment.Carrier.ContactPerson.PhoneNumber	0	..35	0 - 1
Phone number Phone number of the contact person of the carrier.			
1.11.19.8.4.3 Root.Transition.Consignment.Carrier.ContactPerson.EMailAddress	0	..256	0 - 1
E-mail address E-mail address of the contact person of the carrier.			
1.11.19.9 Root.Transition.Consignment.Consignor	0		0 - 1
Details of the consignor			

Identifier	Required/Optional	Format	Iteration
1.11.19.9.1 Root.Transition.Consignment.Consignor.Code	0	..250	0 - 1
Code The reference code for the business partner master data in AC.			
1.11.19.9.2 Root.Transition.Consignment.Consignor.IdentificationNumber	0	..17	0 - 1
Identification number Indication of the EORI number of the consignor.			
1.11.19.9.3 Root.Transition.Consignment.Consignor.SubsidiaryNumber	0	..	0 - 1
Subsidiary number The number of the subsidiary of the carrier (stated by the German customs office).			
1.11.19.9.4 Root.Transition.Consignment.Consignor.Name	0	..70	0 - 1
Name of consignor Name or company name of the consignor			
1.11.19.9.5 Root.Transition.Consignment.Consignor.Address	0		0 - 1
Address data			
1.11.19.9.5.1 Root.Transition.Consignment.Consignor.Address.StreetAndNumber	0	..70	0 - 1
Street and number Street and number of the consignor			
1.11.19.9.5.2 Root.Transition.Consignment.Consignor.Address.Postcode	0	..17	0 - 1
Postcode Postcode of the consignor			
1.11.19.9.5.3 Root.Transition.Consignment.Consignor.Address.City	0	..35	0 - 1
City City of the consignor			
1.11.19.9.5.4 Root.Transition.Consignment.Consignor.Address.Country	0	2	0 - 1
Country ATLAS codelist: C0248 Country code of the address of the consignor.			
1.11.19.9.6 Root.Transition.Consignment.Consignor.ContactPerson	0		0 - 1
Contact person Contact person of the consignor			
1.11.19.9.6.1 Root.Transition.Consignment.Consignor.ContactPerson.Name	0	..70	0 - 1
Name of contact person Name of the contact person of the consignor.			
1.11.19.9.6.2 Root.Transition.Consignment.Consignor.ContactPerson.PhoneNumber	0	..35	0 - 1
Phone number Phone number of the contact person of the consignor.			
1.11.19.9.6.3 Root.Transition.Consignment.Consignor.ContactPerson.EMailAddress	0	..256	0 - 1
E-mail address E-mail address of the contatct person of the consignor.			
1.11.19.10 Root.Transition.Consignment.Consignee	0		0 - 1
Details of the consignee			
1.11.19.10.1 Root.Transition.Consignment.Consignee.Code	0	..250	0 - 1
Code The reference code for the business partner master data in AC.			
1.11.19.10.2 Root.Transition.Consignment.Consignee.IdentificationNumber	0	..17	0 - 1
Identification number Indication of the EORI number of the consignee.			

Identifier	Required/Optional	Format	Iteration
1.11.19.10.3 Root.Transition.Consignment.Consignee.SubsidiaryNumber	0	..	0 - 1
Subsidiary number Number of the subsidiary of the consignee (stated by the German customs office).			
1.11.19.10.4 Root.Transition.Consignment.Consignee.Name	0	..70	0 - 1
Name of consignee Name or company name of the consignee.			
1.11.19.10.5 Root.Transition.Consignment.Consignee.Address	0		0 - 1
Address data			
1.11.19.10.5.1 Root.Transition.Consignment.Consignee.Address.StreetAndNumber	0	..70	0 - 1
Street and number of the consignee.			
1.11.19.10.5.2 Root.Transition.Consignment.Consignee.Address.Postcode	0	..17	0 - 1
Postcode Postcode of the consignee.			
1.11.19.10.5.3 Root.Transition.Consignment.Consignee.Address.City	0	..35	0 - 1
City City of the consignee.			
1.11.19.10.5.4 Root.Transition.Consignment.Consignee.Address.Country	0	2	0 - 1
Country ATLAS code list: C0248 Country code of the address of the consignee.			
1.11.19.10.6 Root.Transition.Consignment.Consignee.ContactPerson	0		0 - 1
Contact person Contact person of the consignee.			
1.11.19.10.6.1 Root.Transition.Consignment.Consignee.ContactPerson.Name	0	..70	0 - 1
Name of contact person Name of the contact person of the consignee.			
1.11.19.10.6.2 Root.Transition.Consignment.Consignee.ContactPerson.PhoneNumber	0	..35	0 - 1
Phone number Phone number of the contact person of the consignee.			
1.11.19.10.6.3 Root.Transition.Consignment.Consignee.ContactPerson.EMailAddress	0	..256	0 - 1
E-mail address E-mail address of the contact person of the consignee.			
1.11.19.11 Root.Transition.Consignment.AdditionalSupplyChainActor	0		0 - 99
Additional actor of the supply chain			
1.11.19.11.1 Root.Transition.Consignment.AdditionalSupplyChainActor.SequenceNumber	0	n....2	0 - 1
Sequence number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.11.2 Root.Transition.Consignment.AdditionalSupplyChainActor.Code	0	..250	0 - 1
Code The reference code for the business partner master data in AC.			
1.11.19.11.3 Root.Transition.Consignment.AdditionalSupplyChainActor.Role	0	..3	0 - 1
Role ATLAS code list: C0704 Role of the additional actor of the supply chain.			
1.11.19.11.4 Root.Transition.Consignment.AdditionalSupplyChainActor.IdentificationNumber	0	..17	0 - 1
Identification number Indication of the EORI number of the additional actor of supply chain			

Identifier	Required/Optional	Format	Iteration
1.11.19.12 Root.Transition.Consignment.TransportEquipment	0		0 - 9999
Transport equipment			
1.11.19.12.1 Root.Transition.Consignment.TransportEquipment.SequenceNumber	0	n....4	0 - 1
Sequence number			
The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.12.2 Root.Transition.Consignment.TransportEquipment.ContainerIdentificationNumber	0	..17	0 - 1
Container number			
Indication of the container number, if data field 'Idicator of conatiner' has been choosen.			
1.11.19.12.3 Root.Transition.Consignment.TransportEquipment.NumberOfSeals	0	n....2	0 - 1
Number of seals			
1.11.19.12.4 Root.Transition.Consignment.TransportEquipment.Seal	0		0 - 99
Seal			
1.11.19.12.4.1 Root.Transition.Consignment.TransportEquipment.Seal.SequenceNumber	0	n....2	0 - 1
Sequence number			
The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.12.4.2 Root.Transition.Consignment.TransportEquipment.Seal.Identifier	0	..20	0 - 1
Seal identifier			
Sign of the seal			
1.11.19.12.5 Root.Transition.Consignment.TransportEquipment.GoodsReference	0		0 - 9999
Goods reference			
Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5 the repeatability is limited to 999.			
1.11.19.12.5.1 Root.Transition.Consignment.TransportEquipment.GoodsReference.SequenceNumber	0	n....4	0 - 1
Sequence number			
The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.12.5.2 Root.Transition.Consignment.TransportEquipment.GoodsReference.DeclarationGoodsItemNumber	0	n....4	0 - 1
Goods item number			
Reference to the goods item number			
Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5 the Number is limited to 999.			
1.11.19.13 Root.Transition.Consignment.LocationOfGoods	0		0 - 1
Location of goods			
Place of Loading of the goods and where potential seals are applied.			
1.11.19.13.1 Root.Transition.Consignment.LocationOfGoods.TypeOfLocation	0	1	0 - 1
Type of location			
ATLAS code list: S0347			
1.11.19.13.2 Root.Transition.Consignment.LocationOfGoods.QualifierOfIdentification	0	1	0 - 1
Qualifier of identification			
ATLAS code list: S0326			
1.11.19.13.3 Root.Transition.Consignment.LocationOfGoods.AdditionalIdentifier	0	4	0 - 1
Additional identifier			
Customs code for the goods location. The code is specified in the authorisation for the related customs office.			
Note: Digit 01-02: Capital letters (a2) Digit 03-04: Sequence number (n2) '01'-'99			
1.11.19.13.4 Root.Transition.Consignment.LocationOfGoods.ContactPerson	0		0 - 1
Contact person			
This information is recommended if this contact person differs from that of the person who created the message.			
1.11.19.13.4.1 Root.Transition.Consignment.LocationOfGoods.ContactPerson.Name	0	..70	0 - 1
Name of contact person			
Name of the contact person for the supervision of the goods location.			

Identifier	Required/Optional	Format	Iteration
1.11.19.13.4.2 Root.Transition.Consignment.LocationOfGoods.ContactPerson.PhoneNumber	0	..35	0 - 1
Phone number Phone number of the contact person for the supervision of the goods location.			
1.11.19.13.4.3 Root.Transition.Consignment.LocationOfGoods.ContactPerson.EmailAddress	0	..256	0 - 1
E-mail address E-mail address of the contact person for the supervision of the goods location.			
1.11.19.14 Root.Transition.Consignment.DepartureTransportMeans	0		0 - 999
Means of transport (departure) Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the following condition before all others: The indication of the data group is required if the data field 'Container indicator' is filled with the value '0' and the field 'Domestic mode of transport' with a value other than '5' (postal items). During the EU-wide transition period from NCTS-P4 to NCTS-P5 the data group may only be specified once, if the data field 'Domestic mode of transport' data field is specified with the value '2' (rail transport).			
1.11.19.14.1 Root.Transition.Consignment.DepartureTransportMeans.SequenceNumber	0	n....3	0 - 1
Sequence number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.14.2 Root.Transition.Consignment.DepartureTransportMeans.TypeOfIdentification	0	..	0 - 1
Type of identification ATLAS code list: C0750 Type of means of transport Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the value '99' is not permitted.			
1.11.19.14.3 Root.Transition.Consignment.DepartureTransportMeans.IdentificationNumber	0	..35	0 - 1
Identify of vehicle License plate of vehicle			
1.11.19.14.4 Root.Transition.Consignment.DepartureTransportMeans.Nationality	0	2	0 - 1
Nationality ATLAS code list: C0165 Nationality of the means of transport			
1.11.19.15 Root.Transition.Consignment.CountryOfRoutingOfConsignment	0		0 - 99
Routing of consignment Identifiers of the countries through which the goods pass in chronological order between the country of the customs office of departure and the country of the customs office of destination.			
1.11.19.15.1 Root.Transition.Consignment.CountryOfRoutingOfConsignment.SequenceNumber	0	n....2	0 - 1
Sequence number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.15.2 Root.Transition.Consignment.CountryOfRoutingOfConsignment.Country	0	2	0 - 1
Country ATLAS code list: C0248 Country code of the country to be crossed on the transport route.			
1.11.19.16 Root.Transition.Consignment.ActiveBorderTransportMeans	0		0 - 9
Active means of transport (border) This information is required if the border of the European Union is to be crossed.			
1.11.19.16.1 Root.Transition.Consignment.ActiveBorderTransportMeans.SequenceNumber	0	n....1	0 - 1
Sequence number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.16.2 Root.Transition.Consignment.ActiveBorderTransportMeans.TypeOfIdentification	0	..	0 - 1
Type of means of transport ATLAS code list: C0219 Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the value '99' is not permitted.			

Identifier	Required/Optional	Format	Iteration
1.11.19.16.3 Root.Transition.Consignment.ActiveBorderTransportMeans.IdentificationNumber	0	..35	0 - 1
Identify of vehicle License plate of vehicle			
1.11.19.16.4 Root.Transition.Consignment.ActiveBorderTransportMeans.Nationality	0	2	0 - 1
Nationality ATLAS code list: C0165 Nationality of the means of transport.			
1.11.19.16.5 Root.Transition.Consignment.ActiveBorderTransportMeans.ConveyanceReferenceNumber	0	..17	0 - 1
Conveyance reference number Vehicle identification of the means of transport, if applicable, voyage number, flight number or journey number.			
1.11.19.16.6 Root.Transition.Consignment.ActiveBorderTransportMeans.CustomsOfficeAtBorderDeclared	0	8	0 - 1
Customs office at border (declared) Border customs office declared for this transit operation.			
1.11.19.17 Root.Transition.Consignment.PlaceOfLoading	0		0 - 1
Place of loading Place where the goods are loaded for carriage Note: The specification of the data group is required if the data field 'Security' is specified with a value other than 'O'.			
1.11.19.17.1 Root.Transition.Consignment.PlaceOfLoading.Country	0	2	0 - 1
Country code ATLAS code list: C0248			
1.11.19.17.2 Root.Transition.Consignment.PlaceOfLoading.Location	0	..35	0 - 1
City/location Place where the goods are loaded.			
1.11.19.18 Root.Transition.Consignment.PlaceOfUnloading	0		0 - 1
Place of unloading Place where the goods are unloaded onto the means of transport used for their carriage. Note: The specification of the data group is required if the data field 'Security' is specified with a value other than 'O'.			
1.11.19.18.1 Root.Transition.Consignment.PlaceOfUnloading.Country	0	2	0 - 1
Country code ATLAS code list: C0248			
1.11.19.18.2 Root.Transition.Consignment.PlaceOfUnloading.Location	0	..35	0 - 1
City/location Place where the goods are unloaded.			
1.11.19.19 Root.Transition.Consignment.PreviousDocument	0		0 - 9999
Details for previous documents			
1.11.19.19.1 Root.Transition.Consignment.PreviousDocument.SequenceNumber	0	n....2	0 - 1
Sequence number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.19.2 Root.Transition.Consignment.PreviousDocument.Type	0	4	0 - 1
Type ATLAS code list: IO933 Type of previous document			
1.11.19.19.3 Root.Transition.Consignment.PreviousDocument.ReferenceNumber	0	..70	0 - 1
Reference number of previous document Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the format of the data field is limited to an..35.			
1.11.19.19.4 Root.Transition.Consignment.PreviousDocument.ComplementOfInformation	0	..35	0 - 1
Description of previous document Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the format of the data field is limited to an..26.			

Identifier	Required/Optional	Format	Iteration
1.11.19.20 Root.Transition.Consignment.SupportingDocument	0		0 - 99
Supporting document Documents, certificates and permits to be presented			
1.11.19.20.1 Root.Transition.Consignment.SupportingDocument.SequenceNumber	0	n....2	0 - 1
Sequence number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.20.2 Root.Transition.Consignment.SupportingDocument.Type	0	4	0 - 1
Type ATLAS code list: IO923 Type of document			
1.11.19.20.3 Root.Transition.Consignment.SupportingDocument.ReferenceNumber	0	..70	0 - 1
Reference number Classification mark or reference number of the document Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the format of the data field is limited to an..35.			
1.11.19.20.4 Root.Transition.Consignment.SupportingDocument.DocumentLineItemNumber	0	n....5	0 - 1
Item number of document line Reference to a numbered entry in the document.			
1.11.19.20.5 Root.Transition.Consignment.SupportingDocument.ComplementOfInformation	0	..35	0 - 1
Description of document Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the format of the data field is limited to an..26.			
1.11.19.21 Root.Transition.Consignment.TransportDocument	0		0 - 99
Transport document Note: The indication of the data group is required and only permissible if the transport document applies to the entire consignment.			
1.11.19.21.1 Root.Transition.Consignment.TransportDocument.SequenceNumber	0	n....2	0 - 1
Sequence number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.21.2 Root.Transition.Consignment.TransportDocument.Type	0	4	0 - 1
Type ATLAS code list: IO943 Type of transport document			
1.11.19.21.3 Root.Transition.Consignment.TransportDocument.ReferenceNumber	0	..70	0 - 1
Reference number of transport document Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the format of the data field is limited to an..35.			
1.11.19.22 Root.Transition.Consignment.AdditionalReference	0		0 - 99
Additional Reference			
1.11.19.22.1 Root.Transition.Consignment.AdditionalReference.SequenceNumber	0	n....2	0 - 1
Sequence number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.22.2 Root.Transition.Consignment.AdditionalReference.Type	0	4	0 - 1
Type ATLAS code list: IO913 Type of an additional reference			
1.11.19.22.3 Root.Transition.Consignment.AdditionalReference.ReferenceNumber	0	..70	0 - 1
Reference number of an additional reference Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the format of the data field is limited to an..35.			
1.11.19.23 Root.Transition.Consignment.AdditionalInformation	0		0 - 99
Additional information			

Identifier	Required/Optional	Format	Iteration
1.11.19.23.1 Root.Transition.Consignment.AdditionalInformation.SequenceNumber	0	n....2	0 - 1
Sequence number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.23.2 Root.Transition.Consignment.AdditionalInformation.Code	0	5	0 - 1
Code ATLAS code list: IO903 Indicator of the special circumstances.			
1.11.19.23.3 Root.Transition.Consignment.AdditionalInformation.Text	0	..512	0 - 1
Text Explanatory text to the special circumstances.			
1.11.19.24 Root.Transition.Consignment.PaymentMethodTransport	0	1	0 - 1
Method of payment ATLAS code list: C0116 Method of payment of transport charges			
1.11.19.25 Root.Transition.Consignment.HouseConsignment	0		0 - 1999
House / single consignment Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the repeatability of the data group is limited to '1'.			
1.11.19.25.1 Root.Transition.Consignment.HouseConsignment.SequenceNumber	0	n....4	0 - 1
Sequence number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.25.2 Root.Transition.Consignment.HouseConsignment.CountryOfDispatch	0	2	0 - 1
Country of dispatch ATLAS code list: C0248 Country code for country of dispatch Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the specification of the data field is not allowed.			
1.11.19.25.3 Root.Transition.Consignment.HouseConsignment.CountryOfDestination	0	2	0 - 1
Country of destination ATLAS code list: C0248 Country code for country of destination Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the specification of the data field is not allowed.			
1.11.19.25.4 Root.Transition.Consignment.HouseConsignment.GrossMass	0	n....16,3	0 - 1
Gross mass Gross mass of the house consignment in kilograms.			
1.11.19.25.5 Root.Transition.Consignment.HouseConsignment.ReferenceNumberUCR	0	..35	0 - 1
Reference number UCR Indication of unique reference number Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the specification of the data field is not allowed.			
1.11.19.25.6 Root.Transition.Consignment.HouseConsignment.Consignor	0		0 - 1
Consignor Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the specification of the data group is not allowed.			
1.11.19.25.6.1 Root.Transition.Consignment.HouseConsignment.Consignor.Code	0	..250	0 - 1
Code The reference code for the business partner master data in AC.			
1.11.19.25.6.2 Root.Transition.Consignment.HouseConsignment.Consignor.IdentificationNumber	0	..17	0 - 1
Identification number Indication of the EORI number of the consignor			

Identifier	Required/Optional	Format	Iteration
1.11.19.25.6.3 Root.Transition.Consignment.HouseConsignment.Consignor.SubsidiaryNumber	0	..	0 - 1
Subsidiary number Number of the subsidiary of the consignor (stated by the German customs office),			
1.11.19.25.6.4 Root.Transition.Consignment.HouseConsignment.Consignor.Name	0	..70	0 - 1
Name Name or company name of the consignor			
1.11.19.25.6.5 Root.Transition.Consignment.HouseConsignment.Consignor.Address	0		0 - 1
Address data			
1.11.19.25.6.5.1 Root.Transition.Consignment.HouseConsignment.Consignor.Address.StreetAndNumber	0	..70	0 - 1
Street and number Street and number of the address of the cosignor			
1.11.19.25.6.5.2 Root.Transition.Consignment.HouseConsignment.Consignor.Address.Postcode	0	..17	0 - 1
Postcode Postcode of the address of the consignor			
1.11.19.25.6.5.3 Root.Transition.Consignment.HouseConsignment.Consignor.Address.City	0	..35	0 - 1
City City of the address of the consignor			
1.11.19.25.6.5.4 Root.Transition.Consignment.HouseConsignment.Consignor.Address.Country	0	2	0 - 1
Country Country code of the address of the consignor			
1.11.19.25.6.6 Root.Transition.Consignment.HouseConsignment.Consignor.ContactPerson	0		0 - 1
Contact person of the consignor			
1.11.19.25.6.6.1 Root.Transition.Consignment.HouseConsignment.Consignor.ContactPerson.Name	0	..70	0 - 1
Name Name of the contact person of the consignor.			
1.11.19.25.6.6.2 Root.Transition.Consignment.HouseConsignment.Consignor.ContactPerson.PhoneNumber	0	..35	0 - 1
Phone number Phone number of the consignor.			
1.11.19.25.6.6.3 Root.Transition.Consignment.HouseConsignment.Consignor.ContactPerson.EMailAddress	0	..256	0 - 1
E-mail address E-mail address of the contact person of the consignor.			
1.11.19.25.7 Root.Transition.Consignment.HouseConsignment.Consignee	0		0 - 1
Consignee Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the specification of the data group is not allowed.			
1.11.19.25.7.1 Root.Transition.Consignment.HouseConsignment.Consignee.Code	0	..250	0 - 1
Code The reference code for the business partner master data in AC.			
1.11.19.25.7.2 Root.Transition.Consignment.HouseConsignment.Consignee.IdentificationNumber	0	..17	0 - 1
Identification number Indication of the EORI number of the consignee.			
1.11.19.25.7.3 Root.Transition.Consignment.HouseConsignment.Consignee.SubsidiaryNumber	0	..	0 - 1
Subsidiary number Number of the subsidiary of the consignee (stated by the German customs office).			
1.11.19.25.7.4 Root.Transition.Consignment.HouseConsignment.Consignee.Name	0	..70	0 - 1
Name of consignee Name or company name of the consignee			
1.11.19.25.7.5 Root.Transition.Consignment.HouseConsignment.Consignee.Address	0		0 - 1
Adress of consignee			

Identifier	Required/Optional	Format	Iteration
1.11.19.25.7.5.1 Root.Transition.Consignment.HouseConsignment.Consignee.Address.StreetAndNumber	0	..70	0 - 1
Street and number of consignee			
1.11.19.25.7.5.2 Root.Transition.Consignment.HouseConsignment.Consignee.Address.Postcode	0	..17	0 - 1
Postcode of the consignee			
1.11.19.25.7.5.3 Root.Transition.Consignment.HouseConsignment.Consignee.Address.City	0	..35	0 - 1
City of the consignee			
1.11.19.25.7.5.4 Root.Transition.Consignment.HouseConsignment.Consignee.Address.Country	0	2	0 - 1
Country			
ATLAS code list: C0248			
Country code of the address of the consignee.			
1.11.19.25.7.6 Root.Transition.Consignment.HouseConsignment.Consignee.ContactPerson	0		0 - 1
Contact person			
Contact person of the consignee.			
1.11.19.25.7.6.1 Root.Transition.Consignment.HouseConsignment.Consignee.ContactPerson.Name	0	..70	0 - 1
Name of consignee			
Name of the contact person of the consignee.			
1.11.19.25.7.6.2 Root.Transition.Consignment.HouseConsignment.Consignee.ContactPerson.PhoneNumber	0	..35	0 - 1
Phone number			
Phone number of the contact person of the consignee.			
1.11.19.25.7.6.3 Root.Transition.Consignment.HouseConsignment.Consignee.ContactPerson.EMailAddress	0	..256	0 - 1
E-mail address			
E-mail address of the contact person of consignee.			
1.11.19.25.8 Root.Transition.Consignment.HouseConsignment.AdditionalSupplyChainActor	0		0 - 99
Additional actor of the supply chain			
1.11.19.25.8.1 Root.Transition.Consignment.HouseConsignment.AdditionalSupplyChainActor.SequenceNumber	0	n....2	0 - 1
Sequence number			
The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.25.8.2 Root.Transition.Consignment.HouseConsignment.AdditionalSupplyChainActor.Role	0	..3	0 - 1
Role			
ATLAS code list: C0704			
Role of the additional actor of the supply chain.			
1.11.19.25.8.3 Root.Transition.Consignment.HouseConsignment.AdditionalSupplyChainActor.Code	0	..250	0 - 1
Code			
The reference code for the business partner master data in AC.			
1.11.19.25.8.4 Root.Transition.Consignment.HouseConsignment.AdditionalSupplyChainActor.IdentificationNumber	0	..17	0 - 1
Identification number			
Indication of the EORI number of the additional actor of supply chain.			
1.11.19.25.9 Root.Transition.Consignment.HouseConsignment.PreviousDocument	0		0 - 99
Previous document			
Details of previous document			
1.11.19.25.9.1 Root.Transition.Consignment.HouseConsignment.PreviousDocument.SequenceNumber	0	n....2	0 - 1
Sequence number			
The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.25.9.2 Root.Transition.Consignment.HouseConsignment.PreviousDocument.Type	0	4	0 - 1
Type			
ATLAS code list: IO935			
Type of previous document			

Identifier	Required/Optional	Format	Iteration
1.11.19.25.9.3 Root.Transition.Consignment.HouseConsignment.PreviousDocument.ReferenceNumber	0	..70	0 - 1
Reference number of previous document			
Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the format of the data field is limited to an..35.			
1.11.19.25.9.4 Root.Transition.Consignment.HouseConsignment.PreviousDocument.ComplementOfInformation	0	..35	0 - 1
Description of previous document			
Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the format of the data field is limited to an..26.			
1.11.19.25.10 Root.Transition.Consignment.HouseConsignment.SupportingDocument	0		0 - 99
Supporting document			
1.11.19.25.10.1 Root.Transition.Consignment.HouseConsignment.SupportingDocument.SequenceNumber	0	n....2	0 - 1
Sequence number			
The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.25.10.2 Root.Transition.Consignment.HouseConsignment.SupportingDocument.Type	0	4	0 - 1
Type			
ATLAS code list: IO925			
Type of document			
1.11.19.25.10.3 Root.Transition.Consignment.HouseConsignment.SupportingDocument.ReferenceNumber	0	..70	0 - 1
Reference number			
Classification mark or reference number of the document.			
Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the format of the data field is limited to an..35.			
1.11.19.25.10.4 Root.Transition.Consignment.HouseConsignment.SupportingDocument.DocumentLineItemNumber	0	n....5	0 - 1
Item number of document line			
Reference to a numbered entry in the document.			
1.11.19.25.10.5 Root.Transition.Consignment.HouseConsignment.SupportingDocument.ComplementOfInformation	0	..35	0 - 1
Description of document			
Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the format of the data field is limited to an..26.			
1.11.19.25.11 Root.Transition.Consignment.HouseConsignment.TransportDocument	0		0 - 99
Transport document			
Note: The indication of the data group is required and only permissible if the transport document applies to the entire consignment.			
1.11.19.25.11.1 Root.Transition.Consignment.HouseConsignment.TransportDocument.SequenceNumber	0	n....2	0 - 1
Sequence number			
The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.25.11.2 Root.Transition.Consignment.HouseConsignment.TransportDocument.Type	0	4	0 - 1
Type			
ATLAS code list: IO945			
Type of transport document			
1.11.19.25.11.3 Root.Transition.Consignment.HouseConsignment.TransportDocument.ReferenceNumber	0	..70	0 - 1
Reference number of transport document			
Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the format of the data field is limited to an..35.			
1.11.19.25.12 Root.Transition.Consignment.HouseConsignment.AdditionalReference	0		0 - 99
Additional Reference			
1.11.19.25.12.1 Root.Transition.Consignment.HouseConsignment.AdditionalReference.SequenceNumber	0	n....2	0 - 1
Sequence number			
The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.25.12.2 Root.Transition.Consignment.HouseConsignment.AdditionalReference.Type	0	4	0 - 1
Type			
ATLAS code list: IO915			
Type of additional reference			

Identifier	Required/Optional	Format	Iteration
1.11.19.25.12.3 Root.Transition.Consignment.HouseConsignment.AdditionalReference.ReferenceNumber	0	..70	0 - 1
Reference number of additional reference			
Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the format of the data field is limited to an..35.			
1.11.19.25.13 Root.Transition.Consignment.HouseConsignment.AdditionalInformation	0		0 - 99
Additional information			
1.11.19.25.13.1 Root.Transition.Consignment.HouseConsignment.AdditionalInformation.SequenceNumber	0	n....2	0 - 1
Sequence number			
The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.25.13.2 Root.Transition.Consignment.HouseConsignment.AdditionalInformation.Code	0	5	0 - 1
Code			
ATLAS code list: IO903			
Indicator of the special circumstances.			
1.11.19.25.13.3 Root.Transition.Consignment.HouseConsignment.AdditionalInformation.Text	0	..512	0 - 1
Text			
Explanatory text to the special circumstances			
1.11.19.25.14 Root.Transition.Consignment.HouseConsignment.PaymentMethodTransport	0	1	0 - 1
Method of payment			
ATLAS code list: C0116			
Method of payment of transport charges			
1.11.19.25.15 Root.Transition.Consignment.HouseConsignment.ConsignmentItem	0		0 - 999
Item of consignment			
Note: The total number of items for a consignment is limited to 1999 for all individual shipments. If this number is reached, no further individual consignments and goods items can be registered.			
1.11.19.25.15.1 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SequenceNumber	0	n....3	0 - 1
Sequence number			
The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.25.15.2 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.DeclarationType	0	..5	0 - 1
Declaration type			
ATLAS code list: S0232			
1.11.19.25.15.3 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CountryOfDispatch	0	2	0 - 1
Country of dispatch			
ATLAS code list: C0248			
Country code for country of dispatch			
1.11.19.25.15.4 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CountryOfDestination	0	2	0 - 1
Country of destination			
ATLAS code list: C0248			
Country code for country of destination			
1.11.19.25.15.5 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.ReferenceNumberUCR	0	..35	0 - 1
Reference number			
Indication of a unique consignment reference			
1.11.19.25.15.6 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee	0		0 - 1
Consignee			
1.11.19.25.15.6.1 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.Code	0	..250	0 - 1
Code			
The reference code for the business partner master data in AC.			
1.11.19.25.15.6.2 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.IdentificationNumber	0	..17	0 - 1
Identification number			
Indication of the EORI number of the consignee			

Identifier	Required/Optional	Format	Iteration
1.11.19.25.15.6.3 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.SubsidiaryNumber	0	..	0 - 1
Subsidiary number Number of the subsidiary of the consignee (stated by the German customs office)			
1.11.19.25.15.6.4 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.Name	0	..70	0 - 1
Name Name or company name of the consignee			
1.11.19.25.15.6.5 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.Address	0		0 - 1
Address of consignee			
1.11.19.25.15.6.5.1 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.Address.StreetAndNumber	0	..70	0 - 1
Street and number of the consignee			
1.11.19.25.15.6.5.2 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.Address.Postcode	0	..17	0 - 1
Postcode of the consignee			
1.11.19.25.15.6.5.3 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.Address.City	0	..35	0 - 1
City of the consignee			
1.11.19.25.15.6.5.4 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.Address.Country	0	2	0 - 1
Country ATLAS code list: C0248 Country code of the address of the consignee			
1.11.19.25.15.6.6 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.ContactPerson	0		0 - 1
Contact person of the consignee			
1.11.19.25.15.6.6.1 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.ContactPerson.Name	0	..70	0 - 1
Name of the contact person of the consignee			
1.11.19.25.15.6.6.2 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.ContactPerson.PhoneNumber	0	..35	0 - 1
Phone number of the contact person of the consignee			
1.11.19.25.15.6.6.3 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Consignee.ContactPerson.EMailAddress	0	..256	0 - 1
E-mail address of the contact person of the consignee			
1.11.19.25.15.7 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalSupplyChainActor	0		0 - 99
Additional actor of the supply chain			
1.11.19.25.15.7.1 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalSupplyChainActor.SequenceNumber	0	n....2	0 - 1
Sequence number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.25.15.7.2 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalSupplyChainActor.Role	0	..3	0 - 1
Role Role of the additional actor of the supply chain			
1.11.19.25.15.7.3 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalSupplyChainActor.Code	0	..250	0 - 1
Code The reference code for the business partner master data in AC.			
1.11.19.25.15.7.4 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalSupplyChainActor.IdentificationNumber	0	..17	0 - 1
Identification number Indication of the EORI number of the additional actor of supply chain			
1.11.19.25.15.8 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.DescriptionOfGoods	0	..512	0 - 1
Description of goods Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the format of the data field is limited to an..280.			
1.11.19.25.15.9 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CusCode	0	9	0 - 1
CUS code (Customs Union and Statistics) ATLAS code list: C0016 The CUS code is an identifier given to assigned to chemical substances and preparations within the framework of the European Customs of Chemical Products (ECICS)			

Identifier	Required/Optional	Format	Iteration
1.11.19.25.15.10 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CommodityCode	0	..	0 - 1
Commodity code			
1.11.19.25.15.11 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.DangerousGoods	0		0 - 99
Dangerous goods			
Details of dangerous goods			
1.11.19.25.15.11.1 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.DangerousGoods.SequenceNumber	0	n....2	0 - 1
Sequence number			
The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.25.15.11.2 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.DangerousGoods.UNNumber	0	..	0 - 1
UN number			
ATLAS code list: C0101			
UN number of dangerous goods			
1.11.19.25.15.12 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.GrossMass	0	n....16,3	0 - 1
Gross mass in kilogram			
The gross mass is the mass of the goods with all their packaging, but excluding transport material and in particular containers			
1.11.19.25.15.13 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.NetMass	0	n....16,6	0 - 1
Net mass in kilogram			
1.11.19.25.15.14 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Packaging	0		0 - 99
Packaging			
The description and identification of packages assigned to a goods item			
1.11.19.25.15.14.1 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Packaging.SequenceNumber	0	n....2	0 - 1
Sequence number			
The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.25.15.14.2 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Packaging.TypeOfPackages	0	2	0 - 1
Type of packages			
ATLAS code list: C0017			
Note: The type of packaging must be indicated if the parent single consignment or the parent item of goods is transmitted as a newly established data group. In the case of by-pack, it is not mandatory that an identical packaging type is indicated for the main package.			
1.11.19.25.15.14.3 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Packaging.NumberOfPackages	0	n....8	0 - 1
Number of packages			
Number of pieces packed in the same type and with the same shipping mark or, in the case of unpacked goods, the number of items covered.			
1.11.19.25.15.14.4 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Packaging.ShippingMarks	0	..512	0 - 1
Shipping marks			
the mark or number with which a package is marked.			
1.11.19.25.15.14.5 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.Packaging.PackageReference	0	n....4	0 - 1
Package reference			
Reference to packages of another item of goods which have been packed together.			
1.11.19.25.15.15 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.PreviousDocument	0		0 - 99
Previous document			
1.11.19.25.15.15.1 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.PreviousDocument.SequenceNumber	0	n....2	0 - 1
Sequence number			
The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.25.15.15.2 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.PreviousDocument.Type	0	4	0 - 1
Type			
ATLAS code list: IO935			
Type of previous document			
1.11.19.25.15.15.3 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.PreviousDocument.ReferenceNumber	0	..70	0 - 1
Reference number of previous document			
Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the format of the data field is limited to an..35.			

Interface description:	NCTS_DE_IN_XML_AI (XML) - Ausgehender Versand - 1.10.0	Creation date 01.06.2026 Created by AC-20-p20.010	Page 30 of 35
------------------------	--	--	---------------

Identifier	Required/Optional	Format	Iteration
1.11.19.25.15.15.4 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.PreviousDocument.GoodsItemNumber	0	n....5	0 - 1
Goods item number (reference)			
1.11.19.25.15.15.5 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.PreviousDocument.ComplementOfInformation	0	..35	0 - 1
Complement of information			
Description of previous document			
Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the format of the data field is limited to an..26.			
1.11.19.25.15.16 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SupportingDocument	0		0 - 99
Supporting document			
1.11.19.25.15.16.1 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SupportingDocument.SequenceNumber	0	n....2	0 - 1
Sequence number			
The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.25.15.16.2 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SupportingDocument.Type	0	4	0 - 1
Type			
ATLAS code list: IO926			
Type of document			
1.11.19.25.15.16.3 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SupportingDocument.ReferenceNumber	0	..70	0 - 1
Reference number			
Classification mark or reference number of the document			
Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the format of the data field is limited to an..35.			
1.11.19.25.15.16.4 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SupportingDocument.DocumentLineItemNumber	0	n....5	0 - 1
Document line item number			
Reference to a numbered entry in the document			
1.11.19.25.15.16.5 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SupportingDocument.ComplementOfInformation	0	..35	0 - 1
Complement of information			
Description of document			
Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the format of the data field is limited to an..26.			
1.11.19.25.15.17 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalReference	0		0 - 99
Additional reference			
1.11.19.25.15.17.1 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalReference.SequenceNumber	0	n....2	0 - 1
Sequence number			
The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.25.15.17.2 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalReference.Type	0	4	0 - 1
Type			
ATLAS code list: IO916			
Type of additional reference			
1.11.19.25.15.17.3 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalReference.ReferenceNumber	0	..70	0 - 1
Reference number			
Reference number of additional reference			
Note: During the EU-wide transition period from NCTS-P4 to NCTS-P5, the format of the data field is limited to an..35.			
1.11.19.25.15.18 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalInformation	0		0 - 99
Additional information			
1.11.19.25.15.18.1 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalInformation.SequenceNumber	0	n....2	0 - 1
Sequence number			
The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			

Interface description:	NCTS_DE_IN_XML_AI (XML) - Ausgehender Versand - 1.10.0	Creation date 01.06.2026 Created by AC-20-p20.010	Page 31 of 35
------------------------	--	--	---------------

Identifier	Required/Optional	Format	Iteration
1.11.19.25.15.18.2 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalInformation.Code	0	5	0 - 1
Code ATLAS code list: IO906 Indicator of the special circumstances			
1.11.19.25.15.18.3 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalInformation.Text	0	..512	0 - 1
Text Explanatory text to the special circumstances			
1.11.19.25.15.19 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.PaymentMethodTransport	0	1	0 - 1
Method of payment of transport charges ATLAS code list: C0116 Method of payment of the transport charges			
1.11.19.25.15.20 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration	0		0 - 1
Summary declaration Discharge of the customs procedure summary declaration Note: The specification of the data group is required and only permissible if a data field 'Item of consignment - previous document - type' with the value 'N337' is registered			
1.11.19.25.15.20.1 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.IdentificationType	0	3	0 - 1
Type of identification ATLAS code list: A1125 Registration numer-related or order key-related identification			
1.11.19.25.15.20.2 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference	0		0 - 999
Goods reference Goods reference of summary declaration			
1.11.19.25.15.20.2.1 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference.SequenceNumber	0	n....3	0 - 1
Sequence number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.25.15.20.2.2 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference.IdentificationByKey	0		0 - 1
Identification by key Indication of the specific classification key Note: The indication of the data group is required and only allowed if 'Summary declaration - type of identification' is indicated with the value 'AWB'.			
1.11.19.25.15.20.2.2.1 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference.IdentificationByKey.Type	0	3	0 - 1
Type ATLAS code list: A1180 Type of specific classification key			
1.11.19.25.15.20.2.2.2 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference.IdentificationByKey.ReferenceNumber	0	..44	0 - 1
Reference number Reference number of specific classification key			
1.11.19.25.15.20.2.2.3 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference.IdentificationByKey.Custodian	0		0 - 1
Custodian Details of the custodian Note: If no custodian is indicated, it is implicitly expressed that the custody is at the official place.			

Interface description:	NCTS_DE_IN_XML_AI (XML) - Ausgehender Versand - 1.10.0	Creation date 01.06.2026 Created by AC-20-p20.010	Page 32 of 35
------------------------	--	--	---------------

Identifier	Required/Optional	Format	Iteration
1.11.19.25.15.20.2.2.3.1 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference.IdentificationByKey.Custodian.Code	0	..250	0 - 1
Code The reference code for the business partner master data in AC.			
1.11.19.25.15.20.2.2.3.2 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference.IdentificationByKey.Custodian.identificationNumber	0	..17	0 - 1
Identification number Indication of the EORI number of the custodian			
1.11.19.25.15.20.2.3 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference.IdentificationByRegistrationNumber	0		0 - 1
Registration number Indication of the registration number Note: The indication of the data group is required and only allowed if 'Summary declaration - type of identification' is indicated with the value 'REG'			
1.11.19.25.15.20.2.3.1 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference.IdentificationByRegistrationNumber.MRN	0	18	0 - 1
MRN Specification of the assigned Master Reference Number (MRN) Note: The indication of the data field is required and only allowed if the data field 'Entry summary declaration - Goods reference - registration number' is not indicated.			
1.11.19.25.15.20.2.3.2 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference.IdentificationByRegistrationNumber.RegistrationNumber	0	21	0 - 1
Registration number Indication of the registration number (Custody stock) Note: The indication of the data field is required and only allowed if the data field 'Entry summary declaration - Goods reference - registration number - MRN' is not indicated.			
1.11.19.25.15.20.2.3.3 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference.IdentificationByRegistrationNumber.GoodsItemNumber	0	n....4	0 - 1
Goods item number Goods reference of summary declaration (Custody stock)			
1.11.19.25.15.20.2.4 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.SummaryDeclaration.GoodsReference.NumberOfPackages	0	n....5	0 - 1
Number of packages Number of packages to be handled			
1.11.19.25.15.21 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing	0		0 - 1
Customs warehousing Discharge of the customs procedure customs warehousing Note: The specification of the data group is required and only permissible if a data field 'Item of consignment - previous document - type' with the value '9DEZ' is registered			
1.11.19.25.15.21.1 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.LRN	0	..35	0 - 1
LRN Internal reference number from the warehouse keeper			
1.11.19.25.15.21.2 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.Authorisation	0		0 - 1
Authorisation Indication of the customs warehouse authorisation			
1.11.19.25.15.21.2.1 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.Authorisation.Type	0	4	0 - 1
Type ATLAS code list: A1258 Type of authorisation			

Interface description:	NCTS_DE_IN_XML_AI (XML) - Ausgehender Versand - 1.10.0	Creation date 01.06.2026 Created by AC-20-p20.010	Page 33 of 35
------------------------	--	--	---------------

Identifier	Required/Optional	Format	Iteration
1.11.19.25.15.21.2.2 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.Authorisation.ReferenceNumber	0	..35	0 - 1
Authorisation reference number The authorisation reference number must be indicated			
1.11.19.25.15.21.3 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference	0		0 - 999
Goods reference Item to be deducted in the bonded warehouse			
1.11.19.25.15.21.3.1 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.SequenceNumber	0	n....3	0 - 1
Sequence number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			
1.11.19.25.15.21.3.2 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.AccessViaATLAS	0	..	0 - 1
Access via ATLAS ATLAS code list: S0029 Indicator whether the consignment was declared via ATLAS			
1.11.19.25.15.21.3.3 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.MRN	0	18	0 - 1
MRN Specification of the assigned Master Reference Number (MRN). Note: The indication of the data field is required and only allowed if the data field 'Customs warehousing - Goods reference - registration number' is not indicated.			
1.11.19.25.15.21.3.4 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.RegistrationNumber	0	..35	0 - 1
Registration number Registration number of warehouse stock Note: The indication of the data field is required and only allowed if the data field 'Customs warehousing - Goods reference - MRN' is not indicated.			
1.11.19.25.15.21.3.5 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.GoodsItemNumber	0	n....5	0 - 1
Goods item number Goods item number of the warehouse stock			
1.11.19.25.15.21.3.6 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.UsualTreatment	0	..	0 - 1
Usual treatment ATLAS code list: S0027 Indicates whether the goods have been subjected to usual treatment			
1.11.19.25.15.21.3.7 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.Complement	0	..100	0 - 1
Complement Additional information			
1.11.19.25.15.21.3.8 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.CommodityCode	0	..	0 - 1
Commodity code			
1.11.19.25.15.21.3.9 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.GoodsReduction	0		0 - 1
Goods reduction Goods reduction (customs warehousing)			
1.11.19.25.15.21.3.9.1 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.GoodsReduction.MeasurementUnitAndQualifier	0	..5	0 - 1
Measurement unit and qualifier ATLAS code list: IO700 Unit of measurement			

Interface description:	NCTS_DE_IN_XML_AI (XML) - Ausgehender Versand - 1.10.0	Creation date 01.06.2026 Created by AC-20-p20.010	Page 34 of 35
------------------------	--	--	---------------

Identifier	Required/Optional	Format	Iteration
1.11.19.25.15.21.3.9.2 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.GoodsReduction.Quantity	0	n....12,3	0 - 1
Quantity			
1.11.19.25.15.21.3.10 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.GoodsReductionAfterTreatment	0		0 - 1
Goods reduction after treatment Indication of quantity after treatment Note: In this data group a quantity may be indicated if the unit of measurement and/or quantity after customary treatment (according to Art. 220 UCC in connection with Annex 71-03 UCC-DA) differ from those in the data group 'Customs warehouse - goods item reference - goods - departure quantity'.			
1.11.19.25.15.21.3.10.1 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.GoodsReductionAfterTreatment.MeasurementUnitAndQualifier	0	..5	0 - 1
Measurement unit and qualifier ATLAS code list: IO700			
1.11.19.25.15.21.3.10.2 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.CustomsWarehousing.GoodsReference.GoodsReductionAfterTreatment.Quantity	0	n....12,3	0 - 1
Quantity			
1.11.19.25.15.22 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing	0		0 - 1
Inward processing Discharge of the customs procedure inward processing Note: The specification of the data group is required and only permissible if a data field 'Item of consignment - previous document - type' with the value '9DEY' is registered.			
1.11.19.25.15.22.1 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing.SimplyGrantedAuthorisation	0	..	0 - 1
Simply granted authorisation ATLAS code list: S0027 Indicator whether the authorisation was applied for and granted on the basis of a customs declaration			
1.11.19.25.15.22.2 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing.Authorisation	0		0 - 1
Authorisation Note: The entry is required and only permitted if the data field 'Inward processing - Simplified authorisation granted' is entered with the value '0'.			
1.11.19.25.15.22.2.1 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing.Authorisation.Type	0	4	0 - 1
Type ATLAS code list: A1259 Type of authorisation			
1.11.19.25.15.22.2.2 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing.Authorisation.ReferenceNumber	0	..35	0 - 1
Authorisation reference number The authorisation reference number must be indicated			
1.11.19.25.15.22.3 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing.CustomsOfficeOfSupervision	0	8	0 - 1
Customs office of supervision ATLAS code list: D0141 Indication of the customs office of supervision Note: The entry is required and only permitted if the data field 'Inward processing - Simplified authorisation granted' is entered with the value '1'.			
1.11.19.25.15.22.4 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing.GoodsReference	0		0 - 999
Goods reference Item to be deducted of the inward processing			
1.11.19.25.15.22.4.1 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing.GoodsReference.SequenceNumber	0	n....3	0 - 1
Sequence number The first sequence starts with the number '1'. Additional numbers must be given in ascending order without gaps.			

Identifier	Required/Optional	Format	Iteration
1.11.19.25.15.22.4.2 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing.GoodsReference.AccessViaATLAS	0	..	0 - 1
Access via ATLAS ATLAS code list: S0029 Indicator whether the consignment was declared via ATLAS			
1.11.19.25.15.22.4.3 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing.GoodsReference.MRN	0	18	0 - 1
MRN Specification of the assigned Master Reference Number (MRN) Note: The indication of the data field is required and only allowed if the data field 'Inward processing - Goods reference - registration number' is not indicated.			
1.11.19.25.15.22.4.4 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing.GoodsReference.RegistrationNumber	0	..35	0 - 1
Registration number Registration number of inward processing Note: The indication of the data field is required and only allowed if the data field 'Inward processing - Goods reference - MRN' is not indicated.			
1.11.19.25.15.22.4.5 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing.GoodsReference.GoodsItemNumber	0	n....5	0 - 1
Goods item number Goods item number of inward processing			
1.11.19.25.15.22.4.6 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InwardProcessing.GoodsReference.GoodsRelatedData	0	..350	0 - 1
Goods related data Goods related data and information			
1.11.19.25.15.23 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.AdditionalId	0	..35	0 - 1
Additional reference number A reference field at item level to indicate an internal reference. (no transmission to ATLAS)			
1.11.19.25.15.24 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.QuantityOfGoods	0	n....12,3	0 - 1
Quantity of goods The indication of the quantity of goods of a goods item. (no transmission to ATLAS)			
1.11.19.25.15.25 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.QuantityOfGoodsMeasurement	0	..5	0 - 1
Unit of measurement of the quantity of goods The indication of the unit of measurement. (no transmission to ATLAS)			
1.11.19.25.15.26 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.ArticleNumber	0	..35	0 - 1
Article number The article number is used to reference the article master data in AC. (no transmission to ATLAS)			
1.11.19.25.15.27 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InvoiceAmount	0	n....15,2	0 - 1
Invoice amount Invoice price of the goods item. (no transmission to ATLAS)			
1.11.19.25.15.28 Root.Transition.Consignment.HouseConsignment.ConsignmentItem.InvoiceCurrency	0	3	0 - 1
Invoice currency The currency of the invoice amount. (no transmission to ATLAS)			